
androidtv Documentation

Release 0.0.66

Jeff Irion

Mar 26, 2022

CONTENTS

1 ADB Setup	1
1.1 1. ADB Server	1
1.2 2. Python ADB Implementation	3
2 androidtv	5
2.1 androidtv package	5
3 Installation	49
4 ADB Intents and Commands	51
5 Acknowledgments	53
6 Indices and tables	55
Python Module Index	57
Index	59

CHAPTER ONE

ADB SETUP

This package works by sending ADB commands to your Android TV / Fire TV device. There are two ways to accomplish this.

1.1 1. ADB Server

androidtv can use a running ADB server to send ADB commands (credit: [pure-python-adb](#)). More info about ADB can be found here: [Android Debug Bridge \(adb\)](#). There are 3 main ways to setup an ADB server.

Note: The ADB server must be connected to your device(s) before starting Home Assistant. Otherwise, the components will not be setup.

1.1.1 1a) Hass.io ADB Addon

For Hass.io users, this is the easiest option. Information about the addon can be found here: [Community Hass.io Add-ons: Android Debug Bridge](#). The configuration for the addon will look like:

```
{  
    "log_level": "info",  
    "devices": [  
        "192.168.0.111",  
        "192.168.0.222"  
    ],  
    "reconnect_timeout": 90,  
    "keys_path": "/config/.android"  
}
```

Your Home Assistant configuration will look like:

```
media_player:  
- platform: androidtv  
  name: Android TV 1  
  host: 192.168.0.111  
  adb_server_ip: 127.0.0.1  
  
media_player:  
- platform: androidtv  
  name: Android TV 2  
  host: 192.168.0.222  
  adb_server_ip: 127.0.0.1
```

1.1.2 1b) Docker Container

Since Home Assistant isn't able to start the connection with the Android device directly, the ADB Server must do it instead. The ADB Server **must already be connected** to the Android device when Home Assistant attempts to access the ADB Server, or else Home Assistant will be unable to set up the Android device.

A modified script provided on the Home Assistant forums ([source](#)) demonstrates an example startup script for a Docker container that will automatically attempt, and continue to connect to a device when run:

Listing 1: `startup.sh`

```
#!/bin/sh

# for a single device, use: DEVICES=("192.168.0.111")
DEVICES=("192.168.0.111" "192.168.0.222")

echo "Starting up ADB..."

while true; do
    adb -a server nod daemon > /dev/null 2>&1
    sleep 10
done &

echo "Server started. Waiting for 30 seconds..."
sleep 30

echo "Connecting to devices."
for device in ${DEVICES[@]}; do
    adb connect $device
done
echo "Done."

while true; do
    for device in ${DEVICES[@]}; do
        adb connect $device > /dev/null 2>&1
    done
    sleep 60
done
```

Assuming the address of the ADB server is 192.168.0.101, your Home Assistant configuration will look like:

```
media_player:
- platform: androidtv
  name: Android TV 1
  host: 192.168.0.111
  adb_server_ip: 192.168.0.101

media_player:
- platform: androidtv
  name: Android TV 2
  host: 192.168.0.222
  adb_server_ip: 192.168.0.101
```

1.1.3 1c) Linux Service

TODO

Your Home Assistant configuration will look like:

```
media_player:
- platform: androidtv
  name: Android TV 1
  host: 192.168.0.111
  adb_server_ip: 127.0.0.1

media_player:
- platform: androidtv
  name: Android TV 2
  host: 192.168.0.222
  adb_server_ip: 127.0.0.1
```

1.2 2. Python ADB Implementation

The second way that androidtv can communicate with devices is using the Python ADB implementation (credit: [adb-shell](#)).

If your device requires ADB authentication, you will need to follow the instructions in the “ADB Authentication” section below. Once you have an authenticated key, this approach does not require any additional setup or addons. However, users with newer devices may find that the ADB connection is unstable. For a Fire TV device, you can try setting the `get_sources` configuration option to `false`. If the problem cannot be resolved, you should use the ADB server option.

Assuming you have 2 devices that require authentication, your configuration will look like this (update the `adbkey` path accordingly):

```
media_player:
- platform: androidtv
  name: Android TV 1
  host: 192.168.0.111
  adbkey: "/config/.android/adbkey"

media_player:
- platform: androidtv
  name: Android TV 2
  host: 192.168.0.222
  adbkey: "/config/.android/adbkey"
```

1.2.1 ADB Authentication

If you get a “Device authentication required, no keys available” error when trying to set up your Android TV or Fire TV, then you’ll need to create an `adbkey` and add its path to your configuration. Follow the instructions on this page to connect to your device from your computer: [Connecting to Fire TV Through adb](#).

Note: In the dialog appearing on your Android TV / Fire TV, you must check the box that says “always allow connections from this device.” ADB authentication in Home Assistant will only work using a trusted key.

Once you’ve successfully connected to your Android TV / Fire TV via the command `adb connect <ipaddress>`, the file `adbkey` will be created on your computer. The default location for this file is (from <https://developer.android.com/studio/command-line/adb>):

- Linux and Mac: \$HOME/.android
- Windows: %userprofile%\android

Copy the `adbkey` file to your Home Assistant folder and add the path to your configuration.

ANDROIDTV

2.1 androidtv package

2.1.1 Subpackages

androidtv.adb_manager package

Submodules

androidtv.adb_manager.adb_manager_async module

Classes to manage ADB connections.

- `ADBPythonAsync` utilizes a Python implementation of the ADB protocol.
- `ADBServerAsync` utilizes an ADB server to communicate with the device.

```
class androidtv.adb_manager.adb_manager_async.ADBPythonAsync(host, port,
                                                               adbkey="",
                                                               signer=None)
```

Bases: object

A manager for ADB connections that uses a Python implementation of the ADB protocol.

Parameters

- `host (str)` – The address of the device; may be an IP address or a host name
- `port (int)` – The device port to which we are connecting (default is 5555)
- `adbkey (str)` – The path to the adbkey file for ADB authentication
- `signer (PythonRSASigner, None)` – The signer for the ADB keys, as loaded by `ADBPythonAsync.load_adbkey()`

property available

Check whether the ADB connection is intact.

Returns Whether or not the ADB connection is intact

Return type bool

async close()

Close the ADB socket connection.

async connect(always_log_errors=True, auth_timeout_s=10.0, transport_timeout_s=1.0)

Connect to an Android TV / Fire TV device.

Parameters

- **always_log_errors** (*bool*) – If True, errors will always be logged; otherwise, errors will only be logged on the first failed reconnect attempt
- **auth_timeout_s** (*float*) – Authentication timeout (in seconds)
- **transport_timeout_s** (*float*) – Transport timeout (in seconds)

Returns Whether or not the connection was successfully established and the device is available

Return type bool

static load_adbkey(adbkey)

Load the ADB keys.

Parameters **adbkey** (*str*) – The path to the adbkey file for ADB authentication

Returns The PythonRSASigner with the key files loaded

Return type PythonRSASigner

async pull(local_path, device_path)

Pull a file from the device using the Python ADB implementation.

Parameters

- **local_path** (*str*) – The path where the file will be saved
- **device_path** (*str*) – The file on the device that will be pulled

async push(local_path, device_path)

Push a file to the device using the Python ADB implementation.

Parameters

- **local_path** (*str*) – The file that will be pushed to the device
- **device_path** (*str*) – The path where the file will be saved on the device

async screencap()

Take a screenshot using the Python ADB implementation.

Returns The screencap as a binary .png image

Return type bytes

async shell(cmd)

Send an ADB command using the Python ADB implementation.

Parameters **cmd** (*str*) – The ADB command to be sent

Returns The response from the device, if there is a response

Return type str, None

```
class androidtv.adb_manager.adb_manager_async.ADBServerAsync(host, port=5555,  
                                         adb_server_ip='',  
                                         adb_server_port=5037)
```

Bases: object

A manager for ADB connections that uses an ADB server.

Parameters

- **host** (*str*) – The address of the device; may be an IP address or a host name
- **port** (*int*) – The device port to which we are connecting (default is 5555)

- **adb_server_ip** (*str*) – The IP address of the ADB server
- **adb_server_port** (*int*) – The port for the ADB server

property available

Check whether the ADB connection is intact.

Returns Whether or not the ADB connection is intact

Return type bool

async close()

Close the ADB server socket connection.

Currently, this doesn't do anything except set `self._available = False`.

async connect(always_log_errors=True)

Connect to an Android TV / Fire TV device.

Parameters `always_log_errors` (`bool`) – If True, errors will always be logged; otherwise, errors will only be logged on the first failed reconnect attempt

Returns Whether or not the connection was successfully established and the device is available

Return type bool

async pull(local_path, device_path)

Pull a file from the device using an ADB server.

Parameters

- **local_path** (*str*) – The path where the file will be saved
- **device_path** (*str*) – The file on the device that will be pulled

async push(local_path, device_path)

Push a file to the device using an ADB server.

Parameters

- **local_path** (*str*) – The file that will be pushed to the device
- **device_path** (*str*) – The path where the file will be saved on the device

async screencap()

Take a screenshot using an ADB server.

Returns The screencap as a binary .png image, or None if there was an `IndexError` exception

Return type bytes, None

async shell(cmd)

Send an ADB command using an ADB server.

Parameters `cmd` (*str*) – The ADB command to be sent

Returns The response from the device, if there is a response

Return type str, None

```
class androidtv.adb_manager.adb_manager_async.AdbDeviceUsbAsync(serial=None,
                                                               port_path=None,
                                                               de-
                                                               fault_transport_timeout_s=None,
                                                               ban-
                                                               ner=None)
```

Bases: object

An async wrapper for the adb-shell AdbDeviceUsb class.

property available

Whether or not an ADB connection to the device has been established.

async close()

Close the connection via the provided transport's `close()` method.

async connect(rsa_keys=None, transport_timeout_s=None, auth_timeout_s=10.0, read_timeout_s=10.0, auth_callback=None)

Establish an ADB connection to the device.

async pull(device_path, local_path, progress_callback=None, transport_timeout_s=None, read_timeout_s=10.0)

Pull a file from the device.

async push(local_path, device_path, st_mode=33272, mtime=0, progress_callback=None, transport_timeout_s=None, read_timeout_s=10.0)

Push a file or directory to the device.

async shell(command, transport_timeout_s=None, read_timeout_s=10.0, timeout_s=None, decode=True)

Send an ADB shell command to the device.

class androidtv.adb_manager.adb_manager_async.ClientAsync(host, port)

Bases: object

An async wrapper for the pure-python-adb Client class.

async device(serial)

Get a DeviceAsync instance.

class androidtv.adb_manager.adb_manager_async.DeviceAsync(device)

Bases: object

An async wrapper for the pure-python-adb Device class.

async pull(device_path, local_path)

Download a file.

async push(local_path, device_path)

Upload a file.

async screencap()

Take a screencap.

async shell(cmd)

Send a shell command.

androidtv.adb_manager.adb_manager_async._acquire(lock, timeout=3.0)

Handle acquisition and release of an `asyncio.Lock` object with a timeout.

Parameters

- **lock** (`asyncio.Lock`) – The lock that we will try to acquire
- **timeout** (`float`) – The timeout in seconds

Yields acquired (bool) – Whether or not the lock was acquired

Raises LockNotAcquiredException – Raised if the lock was not acquired

androidtv.adb_manager.adb_manager_sync module

Classes to manage ADB connections.

- `ADBPythonSync` utilizes a Python implementation of the ADB protocol.
- `ADBSERVERSync` utilizes an ADB server to communicate with the device.

class androidtv.adb_manager.adb_manager_sync.`ADBPythonSync`(*host*, *port*, *adbkey*='',
signer=*None*)

Bases: `object`

A manager for ADB connections that uses a Python implementation of the ADB protocol.

Parameters

- **host** (*str*) – The address of the device; may be an IP address or a host name
- **port** (*int*) – The device port to which we are connecting (default is 5555)
- **adbkey** (*str*) – The path to the adbkey file for ADB authentication
- **signer** (*PythonRSASigner*, *None*) – The signer for the ADB keys, as loaded by `ADBPythonSync.load_adbkey()`

property available

Check whether the ADB connection is intact.

Returns Whether or not the ADB connection is intact

Return type `bool`

close()

Close the ADB socket connection.

connect(always_log_errors=True, auth_timeout_s=10.0, transport_timeout_s=1.0)

Connect to an Android TV / Fire TV device.

Parameters

- **always_log_errors** (*bool*) – If True, errors will always be logged; otherwise, errors will only be logged on the first failed reconnect attempt
- **auth_timeout_s** (*float*) – Authentication timeout (in seconds)
- **transport_timeout_s** (*float*) – Transport timeout (in seconds)

Returns Whether or not the connection was successfully established and the device is available

Return type `bool`

static load_adbkey(adbkey)

Load the ADB keys.

Parameters `adbkey` (*str*) – The path to the adbkey file for ADB authentication

Returns The `PythonRSASigner` with the key files loaded

Return type `PythonRSASigner`

pull(local_path, device_path)

Pull a file from the device using the Python ADB implementation.

Parameters

- **local_path** (*str*) – The path where the file will be saved
- **device_path** (*str*) – The file on the device that will be pulled

push (*local_path*, *device_path*)

Push a file to the device using the Python ADB implementation.

Parameters

- **local_path** (*str*) – The file that will be pushed to the device
- **device_path** (*str*) – The path where the file will be saved on the device

screencap ()

Take a screenshot using the Python ADB implementation.

Returns The screencap as a binary .png image

Return type bytes

shell (*cmd*)

Send an ADB command using the Python ADB implementation.

Parameters **cmd** (*str*) – The ADB command to be sent

Returns The response from the device, if there is a response

Return type str, None

class androidtv.adb_manager.adb_manager_sync.**ADBServerSync** (*host*, *port*=5555,
adb_server_ip=”,
adb_server_port=5037)

Bases: object

A manager for ADB connections that uses an ADB server.

Parameters

- **host** (*str*) – The address of the device; may be an IP address or a host name
- **port** (*int*) – The device port to which we are connecting (default is 5555)
- **adb_server_ip** (*str*) – The IP address of the ADB server
- **adb_server_port** (*int*) – The port for the ADB server

property available

Check whether the ADB connection is intact.

Returns Whether or not the ADB connection is intact

Return type bool

close ()

Close the ADB server socket connection.

Currently, this doesn't do anything except set self._available = False.

connect (*always_log_errors=True*)

Connect to an Android TV / Fire TV device.

Parameters **always_log_errors** (*bool*) – If True, errors will always be logged; otherwise, errors will only be logged on the first failed reconnect attempt

Returns Whether or not the connection was successfully established and the device is available

Return type bool

pull (*local_path*, *device_path*)

Pull a file from the device using an ADB server.

Parameters

- **local_path** (*str*) – The path where the file will be saved
- **device_path** (*str*) – The file on the device that will be pulled

push (*local_path*, *device_path*)
Push a file to the device using an ADB server.

Parameters

- **local_path** (*str*) – The file that will be pushed to the device
- **device_path** (*str*) – The path where the file will be saved on the device

screencap ()
Take a screenshot using an ADB server.

Returns The screencap as a binary .png image, or `None` if there was an `IndexError` exception

Return type bytes, `None`

shell (*cmd*)
Send an ADB command using an ADB server.

Parameters **cmd** (*str*) – The ADB command to be sent

Returns The response from the device, if there is a response

Return type str, `None`

`androidtv.adb_manager.adb_manager_sync.LOCK_KWARGS = {'timeout': 3.0}`
Use a timeout for the ADB threading lock if it is supported

`androidtv.adb_manager.adb_manager_sync._acquire` (*lock*)
Handle acquisition and release of a `threading.Lock` object with `LOCK_KWARGS` keyword arguments.

Parameters **lock** (`threading.Lock`) – The lock that we will try to acquire

Yields **acquired** (*bool*) – Whether or not the lock was acquired

Raises `LockNotAcquiredException` – Raised if the lock was not acquired

Module contents

androidtv.androidtv package

Submodules

androidtv.androidtv.androidtv_async module

Communicate with an Android TV device via ADB over a network.

ADB Debugging must be enabled.

class `androidtv.androidtv.androidtv_async.AndroidTVAsync` (*host*, *port=5555*,
adbkey=”,
adb_server_ip=”,
adb_server_port=5037,
state_detection_rules=None,
signer=None)
Bases: `androidtv.basetv.basetv_async.BaseTVAsync`, `androidtv.androidtv.base_androidtv.BaseAndroidTV`

Representation of an Android TV device.

Parameters

- **host** (*str*) – The address of the device; may be an IP address or a host name
- **port** (*int*) – The device port to which we are connecting (default is 5555)
- **adbkey** (*str*) – The path to the adbkey file for ADB authentication
- **adb_server_ip** (*str*) – The IP address of the ADB server
- **adb_server_port** (*int*) – The port for the ADB server
- **state_detection_rules** (*dict, None*) – A dictionary of rules for determining the state (see [BaseTV](#))
- **signer** (*PythonRSASigner, None*) – The signer for the ADB keys, as loaded by `androidtv.adb_manager.adb_manager_async.ADBPythonAsync.load_adbkey()`

classmethod `from_base` (*base_tv*)

Construct an `AndroidTVAsync` object from a `BaseTVAsync` object.

Parameters `base_tv` ([BaseTVAsync](#)) – The object that will be converted to an `AndroidTVAsync` object

Returns `atv` – The constructed `AndroidTVAsync` object

Return type [AndroidTVAsync](#)

`async get_properties` (*get_running_apps=True, lazy=False*)

Get the properties needed for Home Assistant updates.

Parameters

- **get_running_apps** (*bool*) – Whether or not to get the `running_apps()` property
- **lazy** (*bool*) – Whether or not to continue retrieving properties if the device is off or the screensaver is running

Returns

- **screen_on** (*bool, None*) – Whether or not the device is on, or `None` if it was not determined
- **awake** (*bool, None*) – Whether or not the device is awake (screensaver is not running), or `None` if it was not determined
- **audio_state** (*str, None*) – The audio state, as determined from “dumpsys audio”, or `None` if it was not determined
- **wake_lock_size** (*int, None*) – The size of the current wake lock, or `None` if it was not determined
- **current_app** (*str, None*) – The current app property, or `None` if it was not determined
- **media_session_state** (*int, None*) – The state from the output of `dumpsys media_session`, or `None` if it was not determined
- **audio_output_device** (*str, None*) – The current audio playback device, or `None` if it was not determined
- **is_volume_muted** (*bool, None*) – Whether or not the volume is muted, or `None` if it was not determined
- **volume** (*int, None*) – The absolute volume level, or `None` if it was not determined

- **running_apps** (*list, None*) – A list of the running apps, or `None` if it was not determined
- **hdmi_input** (*str, None*) – The HDMI input, or `None` if it could not be determined

async get_properties_dict (*get_running_apps=True, lazy=True*)

Get the properties needed for Home Assistant updates and return them as a dictionary.

Parameters

- **get_running_apps** (*bool*) – Whether or not to get the `running_apps()` property
- **lazy** (*bool*) – Whether or not to continue retrieving properties if the device is off or the screensaver is running

Returns A dictionary with keys '`screen_on`', '`awake`', '`wake_lock_size`', '`current_app`', '`media_session_state`', '`audio_state`', '`audio_output_device`', '`is_volume_muted`', '`volume`', '`running_apps`', and '`hdmi_input`'

Return type

dict

async update (*get_running_apps=True, lazy=True*)

Get the info needed for a Home Assistant update.

Parameters

- **get_running_apps** (*bool*) – Whether or not to get the `running_apps()` property
- **lazy** (*bool*) – Whether or not to continue retrieving properties if the device is off or the screensaver is running

Returns

- **state** (*str*) – The state of the device
- **current_app** (*str*) – The current running app
- **running_apps** (*list*) – A list of the running apps if `get_running_apps` is `True`, otherwise the list [`current_app`]
- **audio_output_device** (*str*) – The current audio playback device
- **is_volume_muted** (*bool*) – Whether or not the volume is muted
- **volume_level** (*float*) – The volume level (between 0 and 1)

androidtv.androidtv.androidtv_sync module

Communicate with an Android TV device via ADB over a network.

ADB Debugging must be enabled.

```
class androidtv.androidtv.androidtv_sync.AndroidTVSync(host, port=5555, adbkey='', adb_server_ip='', adb_server_port=5037, state_detection_rules=None, signer=None)
Bases: androidtv.basetv.basetv_sync.BaseTWSync, androidtv.androidtv.BaseAndroidTV
```

Representation of an Android TV device.

Parameters

- **host** (*str*) – The address of the device; may be an IP address or a host name

- **port** (*int*) – The device port to which we are connecting (default is 5555)
- **adbkey** (*str*) – The path to the adbkey file for ADB authentication
- **adb_server_ip** (*str*) – The IP address of the ADB server
- **adb_server_port** (*int*) – The port for the ADB server
- **state_detection_rules** (*dict, None*) – A dictionary of rules for determining the state (see [BaseTV](#))
- **signer** (*PythonRSASigner, None*) – The signer for the ADB keys, as loaded by `androidtv.adb_manager.adb_manager_sync.ADBPythonSync.load_adbkey()`

classmethod from_base (*base_tv*)

Construct an *AndroidTVSync* object from a *BaseTVSync* object.

Parameters **base_tv** ([BaseTVSync](#)) – The object that will be converted to an *AndroidTVSync* object

Returns **atv** – The constructed *AndroidTVSync* object

Return type [AndroidTVSync](#)

get_properties (*get_running_apps=True, lazy=False*)

Get the properties needed for Home Assistant updates.

Parameters

- **get_running_apps** (*bool*) – Whether or not to get the `running_apps()` property
- **lazy** (*bool*) – Whether or not to continue retrieving properties if the device is off or the screensaver is running

Returns

- **screen_on** (*bool, None*) – Whether or not the device is on, or `None` if it was not determined
- **awake** (*bool, None*) – Whether or not the device is awake (screensaver is not running), or `None` if it was not determined
- **audio_state** (*str, None*) – The audio state, as determined from “dumpsys audio”, or `None` if it was not determined
- **wake_lock_size** (*int, None*) – The size of the current wake lock, or `None` if it was not determined
- **current_app** (*str, None*) – The current app property, or `None` if it was not determined
- **media_session_state** (*int, None*) – The state from the output of `dumpsys media_session`, or `None` if it was not determined
- **audio_output_device** (*str, None*) – The current audio playback device, or `None` if it was not determined
- **is_volume_muted** (*bool, None*) – Whether or not the volume is muted, or `None` if it was not determined
- **volume** (*int, None*) – The absolute volume level, or `None` if it was not determined
- **running_apps** (*list, None*) – A list of the running apps, or `None` if it was not determined
- **hdmi_input** (*str, None*) – The HDMI input, or `None` if it could not be determined

get_properties_dict (*get_running_apps=True, lazy=True*)

Get the properties needed for Home Assistant updates and return them as a dictionary.

Parameters

- **get_running_apps** (*bool*) – Whether or not to get the `running_apps()` property
- **lazy** (*bool*) – Whether or not to continue retrieving properties if the device is off or the screensaver is running

Returns A dictionary with keys 'screen_on', 'awake', 'wake_lock_size', 'current_app', 'media_session_state', 'audio_state', 'audio_output_device', 'is_volume_muted', 'volume', 'running_apps', and 'hdmi_input'

Return type

dict

update (*get_running_apps=True, lazy=True*)

Get the info needed for a Home Assistant update.

Parameters

- **get_running_apps** (*bool*) – Whether or not to get the `running_apps()` property
- **lazy** (*bool*) – Whether or not to continue retrieving properties if the device is off or the screensaver is running

Returns

- **state** (*str*) – The state of the device
- **current_app** (*str*) – The current running app
- **running_apps** (*list*) – A list of the running apps if `get_running_apps` is True, otherwise the list [`current_app`]
- **audio_output_device** (*str*) – The current audio playback device
- **is_volume_muted** (*bool*) – Whether or not the volume is muted
- **volume_level** (*float*) – The volume level (between 0 and 1)
- **hdmi_input** (*str; None*) – The HDMI input, or `None` if it could not be determined

androidtv.androidtv.base_androidtv module

Communicate with an Android TV device via ADB over a network.

ADB Debugging must be enabled.

```
class androidtv.androidtv.base_androidtv.BaseAndroidTV(host, port=5555, adbkey='', adb_server_ip='', adb_server_port=5037, state_detection_rules=None)
```

Bases: *androidtv.basetv.basetv.BaseTV*

Representation of an Android TV device.

Parameters

- **host** (*str*) – The address of the device; may be an IP address or a host name
- **port** (*int*) – The device port to which we are connecting (default is 5555)
- **adbkey** (*str*) – The path to the `adbkey` file for ADB authentication
- **adb_server_ip** (*str*) – The IP address of the ADB server
- **adb_server_port** (*int*) – The port for the ADB server

- **state_detection_rules** (*dict*, *None*) – A dictionary of rules for determining the state (see *BaseTV*)

```
DEVICE_CLASS = 'androidtv'

DEVICE_ENUM = 1

_update(screen_on, awake, audio_state, wake_lock_size, current_app, media_session_state, audio_output_device, is_volume_muted, volume, running_apps, hdmi_input)
Get the info needed for a Home Assistant update.
```

Parameters

- **screen_on** (*bool*, *None*) – Whether or not the device is on, or *None* if it was not determined
- **awake** (*bool*, *None*) – Whether or not the device is awake (screensaver is not running), or *None* if it was not determined
- **audio_state** (*str*, *None*) – The audio state, as determined from “dumpsys audio”, or *None* if it was not determined
- **wake_lock_size** (*int*, *None*) – The size of the current wake lock, or *None* if it was not determined
- **current_app** (*str*, *None*) – The current app property, or *None* if it was not determined
- **media_session_state** (*int*, *None*) – The state from the output of *dumpsys media_session*, or *None* if it was not determined
- **audio_output_device** (*str*, *None*) – The current audio playback device, or *None* if it was not determined
- **is_volume_muted** (*bool*, *None*) – Whether or not the volume is muted, or *None* if it was not determined
- **volume** (*int*, *None*) – The absolute volume level, or *None* if it was not determined
- **running_apps** (*list*, *None*) – A list of the running apps, or *None* if it was not determined
- **hdmi_input** (*str*, *None*) – The HDMI input, or *None* if it could not be determined

Returns

- **state** (*str*) – The state of the device
- **current_app** (*str*) – The current running app
- **running_apps** (*list*) – A list of the running apps if *get_running_apps* is *True*, otherwise the list [*current_app*]
- **audio_output_device** (*str*) – The current audio playback device
- **is_volume_muted** (*bool*) – Whether or not the volume is muted
- **volume_level** (*float*) – The volume level (between 0 and 1)
- **hdmi_input** (*str*, *None*) – The HDMI input, or *None* if it could not be determined

Module contents

androidtv.basetv package

Submodules

androidtv.basetv.basetv module

Communicate with an Android TV or Amazon Fire TV device via ADB over a network.

ADB Debugging must be enabled.

```
class androidtv.basetv.basetv.BaseTV(adb, host, port=5555, adbkey="", adb_server_ip="",
                                         adb_server_port=5037, state_detection_rules=None)
```

Bases: object

Base class for representing an Android TV / Fire TV device.

The state_detection_rules parameter is of the format:

```
state_detection_rules = {'com.amazon.tv.launcher': ['idle'],
                        'com.netflix.ninja': ['media_session_state'],
                        'com.ellation.vrv': ['audio_state'],
                        'com.hulu.plus': [{('playing'): {'wake_lock_size': 4}},
                                          {('paused'): {'wake_lock_size': 2}}],
                        'com.plexapp.android': [{('paused'): {'media_session_state':
                                          'idle': 3, 'wake_lock_size': 1}},
                                              {('playing'): {'media_session_state':
                                                'idle': 3}}},
```

The keys are app IDs, and the values are lists of rules that are evaluated in order.

VALID_STATES

```
VALID_STATES = ('idle', 'off', 'playing', 'paused', 'standby')
```

Valid rules:

- 'idle', 'playing', 'paused', 'standby', or 'off' = always report the specified state when this app is open
- 'media_session_state' = try to use the media_session_state() property to determine the state
- 'audio_state' = try to use the audio_state() property to determine the state
- { '<VALID_STATE>': { '<PROPERTY1>': VALUE1, '<PROPERTY2>': VALUE2, ... } } = check if each of the properties is equal to the specified value, and if so return the state
 - The valid properties are 'media_session_state', 'audio_state', and 'wake_lock_size'

Parameters

- **adb** (ADBPythonSync, ADBServerSync, ADBPythonAsync, ADBServerAsync) – The handler for ADB commands
- **host** (str) – The address of the device; may be an IP address or a host name
- **port** (int) – The device port to which we are connecting (default is 5555)
- **adbkey** (str) – The path to the adbkey file for ADB authentication
- **adb_server_ip** (str) – The IP address of the ADB server
- **adb_server_port** (int) – The port for the ADB server

- **state_detection_rules** (*dict, None*) – A dictionary of rules for determining the state (see above)

DEVICE_ENUM = 0

static _audio_output_device (*stream_music*)

Get the current audio playback device from the STREAM_MUSIC block from adb shell dumpsys audio.

Parameters **stream_music** (*str, None*) – The STREAM_MUSIC block from adb shell dumpsys audio

Returns The current audio playback device, or `None` if it could not be determined

Return type str, `None`

static _audio_state (*audio_state_response*)

Parse the `audio_state()` property from the ADB shell output.

Parameters **audio_state_response** (*str, None*) – The output from the ADB command `androidtv.basetv.basetv.BaseTV._cmd_audio_state`

Returns The audio state, or `None` if it could not be determined

Return type str, `None`

_cmd_audio_state()

Get the command used to retrieve the current audio state for this device.

Returns The device-specific ADB shell command used to determine the current audio state

Return type str

_cmd_current_app()

Get the command used to retrieve the current app for this device.

Returns The device-specific ADB shell command used to determine the current app

Return type str

_cmd_current_app_media_session_state()

Get the command used to retrieve the current app and media session state for this device.

Returns The device-specific ADB shell command used to determine the current app and media session state

Return type str

_cmd_hdmi_input()

Get the command used to retrieve the current HDMI input for this device.

Returns The device-specific ADB shell command used to determine the current HDMI input

Return type str

_cmd_launch_app (*app*)

Get the command to launch the specified app for this device.

Parameters **app** (*str*) – The app that will be launched

Returns The device-specific command to launch the app

Return type str

_cmd_running_apps()

Get the command used to retrieve the running apps for this device.

Returns The device-specific ADB shell command used to determine the running apps

Return type str

_cmd_turn_off()

Get the command used to turn off this device.

Returns The device-specific ADB shell command used to turn off the device

Return type str

_cmd_turn_on()

Get the command used to turn on this device.

Returns The device-specific ADB shell command used to turn on the device

Return type str

static _conditions_are_true(conditions, media_session_state=None, wake_lock_size=None, audio_state=None)

Check whether the conditions in `conditions` are true.

Parameters

- **conditions** (dict) – A dictionary of conditions to be checked (see the `state_detection_rules` parameter in `BaseTV`)
- **media_session_state** (int, None) – The `media_session_state()` property
- **wake_lock_size** (int, None) – The `wake_lock_size()` property
- **audio_state** (str, None) – The `audio_state()` property

Returns Whether or not all the conditions in `conditions` are true

Return type bool

static _current_app(current_app_response)

Get the current app from the output of the command `androidtv.basetv.basetv.BaseTV._cmd_current_app`.

Parameters `current_app_response` (str, None) – The output from the ADB command `androidtv.basetv.basetv.BaseTV._cmd_current_app`

Returns The current app, or None if it could not be determined

Return type str, None

_current_app_media_session_state(current_app_media_session_state_response)

Get the current app and the media session state properties from the output of `androidtv.basetv.basetv.BaseTV._cmd_current_app_media_session_state`.

Parameters `current_app_media_session_state_response` (str, None) – The output of `androidtv.basetv.basetv.BaseTV._cmd_current_app_media_session_state`

Returns

- **current_app** (str; None) – The current app, or None if it could not be determined
- **media_session_state** (int, None) – The state from the output of the ADB shell command, or None if it could not be determined

_custom_state_detection(current_app=None, media_session_state=None, wake_lock_size=None, audio_state=None)

Use the rules in `self._state_detection_rules` to determine the state.

Parameters

- **current_app** (str, None) – The `current_app()` property
- **media_session_state** (int, None) – The `media_session_state()` property
- **wake_lock_size** (int, None) – The `wake_lock_size()` property
- **audio_state** (str, None) – The `audio_state()` property

Returns The state, if it could be determined using the rules in `self._state_detection_rules`; otherwise, None

Return type str, None

static _get_hdmi_input (`hdmi_response`)

Get the HDMI input from the from the ADB shell output⁴.

Parameters `hdmi_response` (str, None) – The output from the ADB command `androidtv.basetv.basetv.BaseTV._cmd_hdmi_input`

Returns The HDMI input, or None if it could not be determined

Return type str, None

static _get_installed_apps (`installed_apps_response`)

Get the installed apps from the output of `androidtv.constants.CMD_INSTALLED_APPS`.

Parameters `installed_apps_response` (str, None) – The output of `androidtv.constants.CMD_INSTALLED_APPS`

Returns A list of the installed apps, or None if it could not be determined

Return type list, None

static _is_volume_muted (`stream_music`)

Determine whether or not the volume is muted from the STREAM_MUSIC block from adb shell dumpsys audio.

Parameters `stream_music` (str, None) – The STREAM_MUSIC block from adb shell dumpsys audio

Returns Whether or not the volume is muted, or None if it could not be determined

Return type bool, None

_parse_device_properties (`properties`)

Return a dictionary of device properties.

Parameters

- **properties** (str, None) – The output of the ADB command that retrieves the device properties
- **method fills in the device_properties attribute, which is a dictionary with keys** (`This`) –
- 'manufacturer', 'model', and 'sw_version' ('serialno',) –

static _parse_getevent_line (`line`)

Parse a line of the output received in `learn_sendevent`.

Parameters `line` (str) – A line of output from `learn_sendevent`

Returns The properly formatted `sendevent` command

Return type str

static _parse_mac_address (mac_response)

Parse a MAC address from the ADB shell response.

Parameters **mac_response** (*str, None*) – The response from the MAC address ADB shell command

Returns The parsed MAC address, or `None` if it could not be determined

Return type `str, None`

static _parse_stream_music (stream_music_raw)

Parse the output of the command `androidtv.constants.CMD_STREAM_MUSIC`.

Parameters **stream_music_raw** (*str, None*) – The output of the command `androidtv.constants.CMD_STREAM_MUSIC`

Returns The `STREAM_MUSIC` block from the output of `androidtv.constants.CMD_STREAM_MUSIC`, or `None` if it could not be determined

Return type `str, None`

static _remove_adb_shell_prefix (cmd)

Remove the ‘adb shell’ prefix from `cmd`, if present.

Parameters **cmd** (*str*) – The ADB shell command

Returns `cmd` with the ‘adb shell’ prefix removed, if it was present

Return type `str`

static _running_apps (running_apps_response)

Get the running apps from the output of `androidtv.constants.CMD_RUNNING_APPS`.

Parameters **running_apps_response** (*str, None*) – The output of `androidtv.constants.CMD_RUNNING_APPS`

Returns A list of the running apps, or `None` if it could not be determined

Return type `list, None`

static _screen_on_awake_wake_lock_size (output)

Check if the screen is on and the device is awake, and get the wake lock size.

Parameters **output** (*str, None*) – The output from `androidtv.constants.CMD_SCREEN_ON_AWAKE_WAKE_LOCK_SIZE`

Returns

- `bool, None` – Whether or not the device is on, or `None` if it could not be determined
- `bool, None` – Whether or not the device is awake (screensaver is not running), or `None` if it could not be determined
- `int, None` – The size of the current wake lock, or `None` if it could not be determined

_volume (stream_music, audio_output_device)

Get the absolute volume level from the `STREAM_MUSIC` block from adb shell `dumpscreens` `audio`.

Parameters

- **stream_music** (*str, None*) – The `STREAM_MUSIC` block from adb shell `dumpscreens` `audio`
- **audio_output_device** (*str, None*) – The current audio playback device

Returns The absolute volume level, or `None` if it could not be determined

Return type int, None

_volume_level (*volume*)

Get the relative volume level from the absolute volume level.

Parameters **volume** (*int*, *None*) – The absolute volume level

Returns The volume level (between 0 and 1), or *None* if it could not be determined

Return type float, None

static _wake_lock_size (*wake_lock_size_response*)

Get the size of the current wake lock from the output of *androidtv.constants.CMD_WAKE_LOCK_SIZE*.

Parameters **wake_lock_size_response** (*str*, *None*) – The output of *androidtv.constants.CMD_WAKE_LOCK_SIZE*

Returns The size of the current wake lock, or *None* if it could not be determined

Return type int, None

property available

Whether the ADB connection is intact.

Returns Whether or not the ADB connection is intact

Return type bool

customize_command (*custom_command*, *value*)

Customize a command used to retrieve properties.

Parameters

- **custom_command** (*str*) – The name of the command that will be customized; it must be in *constants.CUSTOMIZABLE_COMMANDS*
- **value** (*str*, *None*) – The custom ADB command that will be used, or *None* if the custom command should be deleted

androidtv.basetv.basetv.state_detection_rules_validator (*rules*, *exc=<class 'KeyError'>*)

Validate the rules (i.e., the *state_detection_rules* value) for a given app ID (i.e., a key in *state_detection_rules*).

For each rule in *rules*, this function checks that:

- *rule* is a string or a dictionary
- If *rule* is a string:
 - Check that *rule* is in *VALID_STATES* or *VALID_STATE_PROPERTIES*
- If *rule* is a dictionary:
 - Check that each key is in *VALID_STATES*
 - Check that each value is a dictionary
 - * Check that each key is in *VALID_PROPERTIES*
 - * Check that each value is of the right type, according to *VALID_PROPERTIES_TYPES*

See *BaseTV* for more info about the *state_detection_rules* parameter.

Parameters

- **rules** (*list*) – A list of the rules that will be used to determine the state

- **exc** (*Exception*) – The exception that will be raised if a rule is invalid

Returns **rules** – The provided list of rules

Return type list

androidtv.basetv.basetv_async module

Communicate with an Android TV or Amazon Fire TV device via ADB over a network.

ADB Debugging must be enabled.

```
class androidtv.basetv.basetv_async.BaseTVAsync(host, port=5555, adb_bkey='', adb_server_ip='', adb_server_port=5037, state_detection_rules=None, signer=None)
```

Bases: *androidtv.basetv.basetv.BaseTV*

Base class for representing an Android TV / Fire TV device.

The `state_detection_rules` parameter is of the format:

```
state_detection_rules = {'com.amazon.tv.launcher': ['idle'],
                        'com.netflix.ninja': ['media_session_state'],
                        'com.ellation.vrv': ['audio_state'],
                        'com.hulu.plus': [{('playing'): {'wake_lock_size': 4}},
                                          {('paused'): {'wake_lock_size': 2}}],
                        'com.plexapp.android': [{('paused'): {'media_session_state':
                                          'idle': 3, 'wake_lock_size': 1}},
                                                {('playing'): {'media_session_state':
                                          'idle': 3}}]}
```

The keys are app IDs, and the values are lists of rules that are evaluated in order.

VALID_STATES

```
VALID_STATES = ('idle', 'off', 'playing', 'paused', 'standby')
```

Valid rules:

- 'idle', 'playing', 'paused', 'standby', or 'off' = always report the specified state when this app is open
- 'media_session_state' = try to use the `media_session_state()` property to determine the state
- 'audio_state' = try to use the `audio_state()` property to determine the state
- { '<VALID_STATE>': { '<PROPERTY1>': VALUE1, '<PROPERTY2>': VALUE2, ... } } = check if each of the properties is equal to the specified value, and if so return the state
 - The valid properties are 'media_session_state', 'audio_state', and 'wake_lock_size'

Parameters

- **host** (*str*) – The address of the device; may be an IP address or a host name
- **port** (*int*) – The device port to which we are connecting (default is 5555)

- **adbkey** (*str*) – The path to the adbkey file for ADB authentication
- **adb_server_ip** (*str*) – The IP address of the ADB server
- **adb_server_port** (*int*) – The port for the ADB server
- **state_detection_rules** (*dict, None*) – A dictionary of rules for determining the state (see above)
- **signer** (*PythonRSASigner, None*) – The signer for the ADB keys, as loaded by `androidtv.adb_manager.adb_manager_async.ADBPythonAsync.load_adbkey()`

async _get_stream_music (*stream_music_raw=None*)

Get the STREAM_MUSIC block from the output of the command `androidtv.constants.CMD_STREAM_MUSIC`.

Parameters **stream_music_raw** (*str, None*) – The output of the command `androidtv.constants.CMD_STREAM_MUSIC`

Returns The STREAM_MUSIC block from the output of `androidtv.constants.CMD_STREAM_MUSIC`, or None if it could not be determined

Return type str, None

async _key (*key*)

Send a key event to device.

Parameters **key** (*str, int*) – The Key constant

async _send_intent (*pkg, intent, count=1*)

Send an intent to the device.

Parameters

- **pkg** (*str*) – The command that will be sent is monkey -p <pkg> -c <intent> <count>; echo \$?
- **intent** (*str*) – The command that will be sent is monkey -p <pkg> -c <intent> <count>; echo \$?
- **count** (*int, str*) – The command that will be sent is monkey -p <pkg> -c <intent> <count>; echo \$?

Returns A dictionary with keys 'output' and 'retcode', if they could be determined; otherwise, an empty dictionary

Return type dict

async adb_close ()

Close the ADB connection.

This only works for the Python ADB implementation (see `androidtv.adb_manager.adb_manager_async.ADBPython.close()`). For the ADB server approach, this doesn't do anything (see `androidtv.adb_manager.adb_manager_async.ADBServer.close()`).

async adb_connect (*always_log_errors=True, auth_timeout_s=10.0, transport_timeout_s=1.0*)

Connect to an Android TV / Fire TV device.

Parameters

- **always_log_errors** (*bool*) – If True, errors will always be logged; otherwise, errors will only be logged on the first failed reconnect attempt
- **auth_timeout_s** (*float*) – Authentication timeout (in seconds)

- **transport_timeout_s** (*float*) – Transport timeout (in seconds)

Returns Whether or not the connection was successfully established and the device is available

Return type bool

async adb_pull(*local_path*, *device_path*)

Pull a file from the device.

This calls `androidtv.adb_manager.adb_manager_async.ADBPythonAsync.pull()` or `androidtv.adb_manager.adb_manager_async.ADBServerAsync.pull()`, depending on whether the Python ADB implementation or an ADB server is used for communicating with the device.

Parameters

- **local_path** (*str*) – The path where the file will be saved
- **device_path** (*str*) – The file on the device that will be pulled

async adb_push(*local_path*, *device_path*)

Push a file to the device.

This calls `androidtv.adb_manager.adb_manager_async.ADBPythonAsync.push()` or `androidtv.adb_manager.adb_manager_async.ADBServerAsync.push()`, depending on whether the Python ADB implementation or an ADB server is used for communicating with the device.

Parameters

- **local_path** (*str*) – The file that will be pushed to the device
- **device_path** (*str*) – The path where the file will be saved on the device

async adb_screencap()

Take a screencap.

This calls `androidtv.adb_manager.adb_manager_async.ADBPythonAsync.screencap()` or `androidtv.adb_manager.adb_manager_async.ADBServerAsync.screencap()`, depending on whether the Python ADB implementation or an ADB server is used for communicating with the device.

Returns The screencap as a binary .png image

Return type bytes

async adb_shell(*cmd*)

Send an ADB command.

This calls `androidtv.adb_manager.adb_manager_async.ADBPythonAsync.shell()` or `androidtv.adb_manager.adb_manager_async.ADBServerAsync.shell()`, depending on whether the Python ADB implementation or an ADB server is used for communicating with the device.

Parameters **cmd** (*str*) – The ADB command to be sent

Returns The response from the device, if there is a response

Return type str, None

async audio_output_device()

Get the current audio playback device.

Returns The current audio playback device, or None if it could not be determined

Return type str, None

async audio_state()

Check if audio is playing, paused, or idle.

Returns The audio state, or `None` if it could not be determined

Return type str, `None`

async awake()

Check if the device is awake (screensaver is not running).

Returns Whether or not the device is awake (screensaver is not running)

Return type bool

async back()

Send back action.

async current_app()

Return the current app.

Returns The ID of the current app, or `None` if it could not be determined

Return type str, `None`

async current_app_media_session_state()

Get the current app and the state from the output of `dumppsys media_session`.

Returns

- `str, None` – The current app, or `None` if it could not be determined
- `int, None` – The state from the output of the ADB shell command `dumppsys media_session`, or `None` if it could not be determined

async down()

Send down action.

async enter()

Send enter action.

async get_device_properties()

Return a dictionary of device properties.

Returns `props` – A dictionary with keys '`wifimac`', '`ethmac`', '`serialno`', '`manufacturer`', '`model`', and '`sw_version`'

Return type dict

async get_hdmi_input()

Get the HDMI input from the output of `androidtv.constants.CMD_HDMI_INPUT`.

Returns The HDMI input, or `None` if it could not be determined

Return type str, `None`

async get_installed_apps()

Return a list of installed applications.

Returns A list of the installed apps, or `None` if it could not be determined

Return type list, `None`

async home()

Send home action.

async is_volume_muted()

Whether or not the volume is muted.

Returns Whether or not the volume is muted, or `None` if it could not be determined

Return type bool, None

async key_0()
Send 0 keypress.

async key_1()
Send 1 keypress.

async key_2()
Send 2 keypress.

async key_3()
Send 3 keypress.

async key_4()
Send 4 keypress.

async key_5()
Send 5 keypress.

async key_6()
Send 6 keypress.

async key_7()
Send 7 keypress.

async key_8()
Send 8 keypress.

async key_9()
Send 9 keypress.

async key_a()
Send a keypress.

async key_b()
Send b keypress.

async key_c()
Send c keypress.

async key_d()
Send d keypress.

async key_e()
Send e keypress.

async key_f()
Send f keypress.

async key_g()
Send g keypress.

async key_h()
Send h keypress.

async key_i()
Send i keypress.

async key_j()
Send j keypress.

async key_k()
Send k keypress.

async key_l()
Send l keypress.

async key_m()
Send m keypress.

async key_n()
Send n keypress.

async key_o()
Send o keypress.

async key_p()
Send p keypress.

async key_q()
Send q keypress.

async key_r()
Send r keypress.

async key_s()
Send s keypress.

async key_t()
Send t keypress.

async key_u()
Send u keypress.

async key_v()
Send v keypress.

async key_w()
Send w keypress.

async key_x()
Send x keypress.

async key_y()
Send y keypress.

async key_z()
Send z keypress.

async launch_app(app)
Launch an app.

Parameters `app (str)` – The ID of the app that will be launched

async learn_sendevent(timeout_s=8)

Capture an event (e.g., a button press) via getevent and convert it into sendevent commands.

For more info, see:

- <http://ktnr74.blogspot.com/2013/06/emulating-touchscreen-interaction-with.html?m=1>
- <https://qatesttech.wordpress.com/2012/06/21/turning-the-output-from-getevent-into-something-something-that-can-be/>

Parameters `timeout_s (int)` – The timeout in seconds to wait for events

Returns The events converted to sendevent commands

Return type str

async left()

Send left action.

async media_next_track()

Send media next action (results in fast-forward).

async media_pause()

Send media pause action.

async media_play()

Send media play action.

async media_play_pause()

Send media play/pause action.

async media_previous_track()

Send media previous action (results in rewind).

async media_session_state()

Get the state from the output of dumpsys media_session.

Returns The state from the output of the ADB shell command dumpsys media_session, or None if it could not be determined

Return type int, None

async media_stop()

Send media stop action.

async menu()

Send menu action.

async mute_volume()

Mute the volume.

async power()

Send power action.

async right()

Send right action.

async running_apps()

Return a list of running user applications.

Returns A list of the running apps

Return type list

async screen_on()

Check if the screen is on.

Returns Whether or not the device is on

Return type bool

async screen_on_awake_wake_lock_size()

Check if the screen is on and the device is awake, and get the wake lock size.

Returns

- *bool* – Whether or not the device is on
- *bool* – Whether or not the device is awake (screensaver is not running)
- *int, None* – The size of the current wake lock, or None if it could not be determined

async set_volume_level(*volume_level*)

Set the volume to the desired level.

Parameters **volume_level** (*float*) – The new volume level (between 0 and 1)

Returns The new volume level (between 0 and 1), or None if self.max_volume could not be determined

Return type float, None

async sleep()

Send sleep action.

async space()

Send space keypress.

async start_intent(*uri*)

Start an intent on the device.

Parameters **uri** (*str*) – The intent that will be sent is am start -a android.intent.action.VIEW -d <uri>

async stop_app(*app*)

Stop an app.

Parameters **app** (*str*) – The ID of the app that will be stopped

Returns The output of the am force-stop ADB shell command, or None if the device is unavailable

Return type str, None

async stream_music_properties()

Get various properties from the “STREAM_MUSIC” block from dumpsys audio..

Returns

- **audio_output_device** (*str, None*) – The current audio playback device, or None if it could not be determined
- **is_volume_muted** (*bool, None*) – Whether or not the volume is muted, or None if it could not be determined
- **volume** (*int, None*) – The absolute volume level, or None if it could not be determined
- **volume_level** (*float, None*) – The volume level (between 0 and 1), or None if it could not be determined

async turn_off()

Turn off the device.

async turn_on()

Turn on the device.

async up()

Send up action.

async volume()

Get the absolute volume level.

Returns The absolute volume level, or None if it could not be determined

Return type int, None

async volume_down(*current_volume_level=None*)

Send volume down action.

Parameters `current_volume_level` (`float, None`) – The current volume level (between 0 and 1); if it is not provided, it will be determined

Returns The new volume level (between 0 and 1), or `None` if `self.max_volume` could not be determined

Return type `float, None`

`async volume_level()`

Get the relative volume level.

Returns The volume level (between 0 and 1), or `None` if it could not be determined

Return type `float, None`

`async volume_up(current_volume_level=None)`

Send volume up action.

Parameters `current_volume_level` (`float, None`) – The current volume level (between 0 and 1); if it is not provided, it will be determined

Returns The new volume level (between 0 and 1), or `None` if `self.max_volume` could not be determined

Return type `float, None`

`async wake_lock_size()`

Get the size of the current wake lock.

Returns The size of the current wake lock, or `None` if it could not be determined

Return type `int, None`

androidtv.basetv.basetv_sync module

Communicate with an Android TV or Amazon Fire TV device via ADB over a network.

ADB Debugging must be enabled.

```
class androidtv.basetv.basetv_sync.BaseTWSync(host, port=5555, adb_server_ip='', adb_server_port=5037, state_detection_rules=None, signer=None)
```

Bases: `androidtv.basetv.basetv.BaseTV`

Base class for representing an Android TV / Fire TV device.

The `state_detection_rules` parameter is of the format:

```
state_detection_rules = {'com.amazon.tv.launcher': ['idle'],
                        'com.netflix.ninja': ['media_session_state'],
                        'com.ellation.vrv': ['audio_state'],
                        'com.hulu.plus': [{('playing'): {'wake_lock_size': 4}},
                                         {('paused'): {'wake_lock_size': 2}}],
                        'com.plexapp.android': [{('paused'): {'media_session_state':
                                         3, 'wake_lock_size': 1}},
                                         {('playing'): {'media_session_state':
                                         3}}],}
                                         'idle'])}
```

The keys are app IDs, and the values are lists of rules that are evaluated in order.

VALID_STATES

```
VALID_STATES = ('idle', 'off', 'playing', 'paused', 'standby')
```

Valid rules:

- 'idle', 'playing', 'paused', 'standby', or 'off' = always report the specified state when this app is open
- 'media_session_state' = try to use the `media_session_state()` property to determine the state
- 'audio_state' = try to use the `audio_state()` property to determine the state
- { '<VALID_STATE>': { '<PROPERTY1>': VALUE1, '<PROPERTY2>': VALUE2, ... } } = check if each of the properties is equal to the specified value, and if so return the state
 - The valid properties are 'media_session_state', 'audio_state', and 'wake_lock_size'

Parameters

- **host** (*str*) – The address of the device; may be an IP address or a host name
- **port** (*int*) – The device port to which we are connecting (default is 5555)
- **adbkey** (*str*) – The path to the adbkey file for ADB authentication
- **adb_server_ip** (*str*) – The IP address of the ADB server
- **adb_server_port** (*int*) – The port for the ADB server
- **state_detection_rules** (*dict, None*) – A dictionary of rules for determining the state (see above)
- **signer** (*PythonRSASigner, None*) – The signer for the ADB keys, as loaded by `androidtv.adb_manager.adb_manager_sync.ADBPythonSync.load_adbkey()`

_get_stream_music(stream_music_raw=None)

Get the STREAM_MUSIC block from the output of the command `androidtv.constants.CMD_STREAM_MUSIC`.

Parameters **stream_music_raw** (*str, None*) – The output of the command `androidtv.constants.CMD_STREAM_MUSIC`

Returns The STREAM_MUSIC block from the output of `androidtv.constants.CMD_STREAM_MUSIC`, or None if it could not be determined

Return type str, None

_key(key)

Send a key event to device.

Parameters **key** (*str, int*) – The Key constant

_send_intent(pkg, intent, count=1)

Send an intent to the device.

Parameters

- **pkg** (*str*) – The command that will be sent is monkey -p <pkg> -c <intent> <count>; echo \$?

- **intent** (*str*) – The command that will be sent is monkey -p <pkg> -c <intent> <count>; echo \$?
- **count** (*int, str*) – The command that will be sent is monkey -p <pkg> -c <intent> <count>; echo \$?

Returns A dictionary with keys 'output' and 'retcode', if they could be determined; otherwise, an empty dictionary

Return type dict

adb_close()

Close the ADB connection.

This only works for the Python ADB implementation (see [androidtv.adb_manager.adb_manager_sync.ADBPythonSync.close\(\)](#)). For the ADB server approach, this doesn't do anything (see [androidtv.adb_manager.adb_manager_sync.ADBServerSync.close\(\)](#)).

adb_connect (always_log_errors=True, auth_timeout_s=10.0, transport_timeout_s=1.0)

Connect to an Android TV / Fire TV device.

Parameters

- **always_log_errors** (*bool*) – If True, errors will always be logged; otherwise, errors will only be logged on the first failed reconnect attempt
- **auth_timeout_s** (*float*) – Authentication timeout (in seconds)
- **transport_timeout_s** (*float*) – Transport timeout (in seconds)

Returns Whether or not the connection was successfully established and the device is available

Return type bool

adb_pull (local_path, device_path)

Pull a file from the device.

This calls [androidtv.adb_manager.adb_manager_sync.ADBPythonSync.pull\(\)](#) or [androidtv.adb_manager.adb_manager_sync.ADBServerSync.pull\(\)](#), depending on whether the Python ADB implementation or an ADB server is used for communicating with the device.

Parameters

- **local_path** (*str*) – The path where the file will be saved
- **device_path** (*str*) – The file on the device that will be pulled

adb_push (local_path, device_path)

Push a file to the device.

This calls [androidtv.adb_manager.adb_manager_sync.ADBPythonSync.push\(\)](#) or [androidtv.adb_manager.adb_manager_sync.ADBServerSync.push\(\)](#), depending on whether the Python ADB implementation or an ADB server is used for communicating with the device.

Parameters

- **local_path** (*str*) – The file that will be pushed to the device
- **device_path** (*str*) – The path where the file will be saved on the device

adb_screencap()

Take a screencap.

This calls `androidtv.adb_manager.adb_manager_sync.ADBPythonSync.screencap()` or `androidtv.adb_manager.adb_manager_sync.ADBServerSync.screencap()`, depending on whether the Python ADB implementation or an ADB server is used for communicating with the device.

Returns The screencap as a binary .png image

Return type bytes

`adb_shell(cmd)`

Send an ADB command.

This calls `androidtv.adb_manager.adb_manager_sync.ADBPythonSync.shell()` or `androidtv.adb_manager.adb_manager_sync.ADBServerSync.shell()`, depending on whether the Python ADB implementation or an ADB server is used for communicating with the device.

Parameters `cmd(str)` – The ADB command to be sent

Returns The response from the device, if there is a response

Return type str, None

`audio_output_device()`

Get the current audio playback device.

Returns The current audio playback device, or None if it could not be determined

Return type str, None

`audio_state()`

Check if audio is playing, paused, or idle.

Returns The audio state, or None if it could not be determined

Return type str, None

`awake()`

Check if the device is awake (screensaver is not running).

Returns Whether or not the device is awake (screensaver is not running)

Return type bool

`back()`

Send back action.

`current_app()`

Return the current app.

Returns The ID of the current app, or None if it could not be determined

Return type str, None

`current_app_media_session_state()`

Get the current app and the state from the output of `dumpsys media_session`.

Returns

- `str, None` – The current app, or None if it could not be determined
- `int, None` – The state from the output of the ADB shell command `dumpsys media_session`, or None if it could not be determined

`down()`

Send down action.

```
enter()
    Send enter action.

get_device_properties()
    Return a dictionary of device properties.

    Returns props – A dictionary with keys 'wifimac', 'ethmac', 'serialno',
    'manufacturer', 'model', and 'sw_version'

    Return type dict

get_hdmi_input()
    Get the HDMI input from the output of androidtv.constants.CMD_HDMI_INPUT.

    Returns The HDMI input, or None if it could not be determined

    Return type str, None

get_installed_apps()
    Return a list of installed applications.

    Returns A list of the installed apps, or None if it could not be determined

    Return type list, None

home()
    Send home action.

is_volume_muted()
    Whether or not the volume is muted.

    Returns Whether or not the volume is muted, or None if it could not be determined

    Return type bool, None

key_0()
    Send 0 keypress.

key_1()
    Send 1 keypress.

key_2()
    Send 2 keypress.

key_3()
    Send 3 keypress.

key_4()
    Send 4 keypress.

key_5()
    Send 5 keypress.

key_6()
    Send 6 keypress.

key_7()
    Send 7 keypress.

key_8()
    Send 8 keypress.

key_9()
    Send 9 keypress.
```

key_a()
Send a keypress.

key_b()
Send b keypress.

key_c()
Send c keypress.

key_d()
Send d keypress.

key_e()
Send e keypress.

key_f()
Send f keypress.

key_g()
Send g keypress.

key_h()
Send h keypress.

key_i()
Send i keypress.

key_j()
Send j keypress.

key_k()
Send k keypress.

key_l()
Send l keypress.

key_m()
Send m keypress.

key_n()
Send n keypress.

key_o()
Send o keypress.

key_p()
Send p keypress.

key_q()
Send q keypress.

key_r()
Send r keypress.

key_s()
Send s keypress.

key_t()
Send t keypress.

key_u()
Send u keypress.

key_v()
Send v keypress.

key_w()
Send w keypress.

key_x()
Send x keypress.

key_y()
Send y keypress.

key_z()
Send z keypress.

launch_app(app)
Launch an app.

Parameters `app` (*str*) – The ID of the app that will be launched

learn_sendevent(timeout_s=8)
Capture an event (e.g., a button press) via `getevent` and convert it into `sendevent` commands.

For more info, see:

- <http://ktnr74.blogspot.com/2013/06/emulating-touchscreen-interaction-with.html?m=1>
- <https://qatesttech.wordpress.com/2012/06/21/turning-the-output-from-getevent-into-something-something-that-can-be/>

Parameters `timeout_s` (*int*) – The timeout in seconds to wait for events

Returns The events converted to `sendevent` commands

Return type `str`

left()
Send left action.

media_next_track()
Send media next action (results in fast-forward).

media_pause()
Send media pause action.

media_play()
Send media play action.

media_play_pause()
Send media play/pause action.

media_previous_track()
Send media previous action (results in rewind).

media_session_state()
Get the state from the output of `dumpsys media_session`.

Returns The state from the output of the ADB shell command `dumpsys media_session`, or `None` if it could not be determined

Return type `int, None`

media_stop()
Send media stop action.

menu()
Send menu action.

mute_volume()
Mute the volume.

power()
Send power action.

right()
Send right action.

running_apps()
Return a list of running user applications.

Returns A list of the running apps

Return type list

screen_on()
Check if the screen is on.

Returns Whether or not the device is on

Return type bool

screen_on_awake_wake_lock_size()
Check if the screen is on and the device is awake, and get the wake lock size.

Returns

- *bool* – Whether or not the device is on
- *bool* – Whether or not the device is awake (screensaver is not running)
- *int, None* – The size of the current wake lock, or *None* if it could not be determined

set_volume_level(*volume_level*)
Set the volume to the desired level.

Parameters **volume_level** (*float*) – The new volume level (between 0 and 1)

Returns The new volume level (between 0 and 1), or *None* if *self.max_volume* could not be determined

Return type float, None

sleep()
Send sleep action.

space()
Send space keypress.

start_intent(*uri*)
Start an intent on the device.

Parameters **uri** (*str*) – The intent that will be sent is `am start -a android.intent.action.VIEW -d <uri>`

stop_app(*app*)
Stop an app.

Parameters **app** (*str*) – The ID of the app that will be stopped

Returns The output of the `am force-stop` ADB shell command, or *None* if the device is unavailable

Return type str, None

stream_music_properties()

Get various properties from the “STREAM_MUSIC” block from dumpsys audio..

Returns

- **audio_output_device** (*str, None*) – The current audio playback device, or *None* if it could not be determined
- **is_volume_muted** (*bool, None*) – Whether or not the volume is muted, or *None* if it could not be determined
- **volume** (*int, None*) – The absolute volume level, or *None* if it could not be determined
- **volume_level** (*float, None*) – The volume level (between 0 and 1), or *None* if it could not be determined

turn_off()

Turn off the device.

turn_on()

Turn on the device.

up()

Send up action.

volume()

Get the absolute volume level.

Returns The absolute volume level, or *None* if it could not be determined

Return type int, None

volume_down(*current_volume_level=None*)

Send volume down action.

Parameters **current_volume_level** (*float, None*) – The current volume level (between 0 and 1); if it is not provided, it will be determined

Returns The new volume level (between 0 and 1), or *None* if *self.max_volume* could not be determined

Return type float, None

volume_level()

Get the relative volume level.

Returns The volume level (between 0 and 1), or *None* if it could not be determined

Return type float, None

volume_up(*current_volume_level=None*)

Send volume up action.

Parameters **current_volume_level** (*float, None*) – The current volume level (between 0 and 1); if it is not provided, it will be determined

Returns The new volume level (between 0 and 1), or *None* if *self.max_volume* could not be determined

Return type float, None

wake_lock_size()

Get the size of the current wake lock.

Returns The size of the current wake lock, or `None` if it could not be determined

Return type int, `None`

Module contents

androidtv.firetv package

Submodules

androidtv.firetv.base_firetv module

Communicate with an Amazon Fire TV device via ADB over a network.

ADB Debugging must be enabled.

```
class androidtv.firetv.base_firetv.BaseFireTV(host, port=5555,
                                                bkey='', adb_server_ip='',
                                                adb_server_port=5037,
                                                state_detection_rules=None)
```

Bases: `androidtv.basetv.basetv.BaseTV`

Representation of an Amazon Fire TV device.

Parameters

- **host** (`str`) – The address of the device; may be an IP address or a host name
- **port** (`int`) – The device port to which we are connecting (default is 5555)
- **adbkey** (`str`) – The path to the `adbkey` file for ADB authentication
- **adb_server_ip** (`str`) – The IP address of the ADB server
- **adb_server_port** (`int`) – The port for the ADB server
- **state_detection_rules** (`dict, None`) – A dictionary of rules for determining the state (see `BaseTV`)

```
DEVICE_CLASS = 'firetv'
```

```
DEVICE_ENUM = 2
```

```
_update(screen_on, awake, wake_lock_size, current_app, media_session_state, running_apps,
        hdmi_input)
```

Get the info needed for a Home Assistant update.

Parameters

- **screen_on** (`bool, None`) – Whether or not the device is on, or `None` if it was not determined
- **awake** (`bool, None`) – Whether or not the device is awake (screensaver is not running), or `None` if it was not determined
- **wake_lock_size** (`int, None`) – The size of the current wake lock, or `None` if it was not determined
- **current_app** (`str, None`) – The current app property, or `None` if it was not determined
- **media_session_state** (`int, None`) – The state from the output of `dumpsyst media_session`, or `None` if it was not determined

- **running_apps** (*list*, *None*) – A list of the running apps, or *None* if it was not determined
- **hdmi_input** (*str*, *None*) – The HDMI input, or *None* if it could not be determined

Returns

- **state** (*str*) – The state of the device
- **current_app** (*str*) – The current running app
- **running_apps** (*list*) – A list of the running apps if `get_running_apps` is `True`, otherwise the list [`current_app`]
- **hdmi_input** (*str*, *None*) – The HDMI input, or *None* if it could not be determined

androidtv.firetv.firetv_async module

Communicate with an Amazon Fire TV device via ADB over a network.

ADB Debugging must be enabled.

```
class androidtv.firetv.firetv_async.FireTVAsync(host, port=5555, adbkey='', adb_server_ip='', adb_server_port=5037, state_detection_rules=None, signer=None)
Bases: androidtv.basetv.basetv_async.BaseTVAsync, androidtv.firetv.base_firetv.BaseFireTV
```

Representation of an Amazon Fire TV device.

Parameters

- **host** (*str*) – The address of the device; may be an IP address or a host name
- **port** (*int*) – The device port to which we are connecting (default is 5555)
- **adbkey** (*str*) – The path to the `adbkey` file for ADB authentication
- **adb_server_ip** (*str*) – The IP address of the ADB server
- **adb_server_port** (*int*) – The port for the ADB server
- **state_detection_rules** (*dict*, *None*) – A dictionary of rules for determining the state (see `BaseTV`)
- **signer** (*PythonRSASigner*, *None*) – The signer for the ADB keys, as loaded by `androidtv.adb_manager.adb_manager_async.ADBPythonAsync.load_adbkey()`

```
classmethod from_base(base_tv)
```

Construct a `FireTVAsync` object from a `BaseTVAsync` object.

Parameters **base_tv** (`BaseTVAsync`) – The object that will be converted to a `FireTVAsync` object

Returns **ftv** – The constructed `FireTVAsync` object

Return type `FireTVAsync`

```
async get_properties(get_running_apps=True, lazy=False)
```

Get the properties needed for Home Assistant updates.

Parameters

- **get_running_apps (bool)** – Whether or not to get the `running_apps ()` property
- **lazy (bool)** – Whether or not to continue retrieving properties if the device is off or the screensaver is running

Returns

- **screen_on (bool, None)** – Whether or not the device is on, or `None` if it was not determined
- **awake (bool, None)** – Whether or not the device is awake (screensaver is not running), or `None` if it was not determined
- **wake_lock_size (int, None)** – The size of the current wake lock, or `None` if it was not determined
- **current_app (str, None)** – The current app property, or `None` if it was not determined
- **media_session_state (int, None)** – The state from the output of `dumpsyst media_session`, or `None` if it was not determined
- **running_apps (list, None)** – A list of the running apps, or `None` if it was not determined
- **hdmi_input (str, None)** – The HDMI input, or `None` if it could not be determined

async get_properties_dict (get_running_apps=True, lazy=True)

Get the properties needed for Home Assistant updates and return them as a dictionary.

Parameters

- **get_running_apps (bool)** – Whether or not to get the `running_apps ()` property
- **lazy (bool)** – Whether or not to continue retrieving properties if the device is off or the screensaver is running

Returns A dictionary with keys '`screen_on`', '`awake`', '`wake_lock_size`', '`current_app`', '`media_session_state`', '`running_apps`', and '`hdmi_input`'

Return type dict

async update (get_running_apps=True, lazy=True)

Get the info needed for a Home Assistant update.

Parameters

- **get_running_apps (bool)** – Whether or not to get the `running_apps ()` property
- **lazy (bool)** – Whether or not to continue retrieving properties if the device is off or the screensaver is running

Returns

- **state (str)** – The state of the device
- **current_app (str)** – The current running app
- **running_apps (list)** – A list of the running apps if `get_running_apps` is True, otherwise the list [`current_app`]
- **hdmi_input (str, None)** – The HDMI input, or `None` if it could not be determined

androidtv.firetv.firetv_sync module

Communicate with an Amazon Fire TV device via ADB over a network.

ADB Debugging must be enabled.

```
class androidtv.firetv.firetv_sync.FireTVSync(host, port=5555, adb_key='', adb_server_ip='', adb_server_port=5037, state_detection_rules=None, signer=None)
Bases: androidtv.basetv.basetv_sync.BaseTVSync, androidtv.firetv.base_firetv.BaseFireTV
```

Representation of an Amazon Fire TV device.

Parameters

- **host** (*str*) – The address of the device; may be an IP address or a host name
- **port** (*int*) – The device port to which we are connecting (default is 5555)
- **adbkey** (*str*) – The path to the adbkey file for ADB authentication
- **adb_server_ip** (*str*) – The IP address of the ADB server
- **adb_server_port** (*int*) – The port for the ADB server
- **state_detection_rules** (*dict, None*) – A dictionary of rules for determining the state (see [BaseTV](#))
- **signer** (*PythonRSASigner, None*) – The signer for the ADB keys, as loaded by [androidtv.adb_manager.adb_manager_sync.ADBPythonSync.load_adbkey\(\)](#)

```
classmethod from_base(base_tv)
```

Construct a *FireTVSync* object from a *BaseTVSync* object.

Parameters **base_tv** ([BaseTVSync](#)) – The object that will be converted to a *FireTVSync* object

Returns **ftv** – The constructed *FireTVSync* object

Return type [FireTVSync](#)

```
get_properties(get_running_apps=True, lazy=False)
```

Get the properties needed for Home Assistant updates.

Parameters

- **get_running_apps** (*bool*) – Whether or not to get the `running_apps()` property
- **lazy** (*bool*) – Whether or not to continue retrieving properties if the device is off or the screensaver is running

Returns

- **screen_on** (*bool, None*) – Whether or not the device is on, or *None* if it was not determined
- **awake** (*bool, None*) – Whether or not the device is awake (screensaver is not running), or *None* if it was not determined
- **wake_lock_size** (*int, None*) – The size of the current wake lock, or *None* if it was not determined
- **current_app** (*str, None*) – The current app property, or *None* if it was not determined
- **media_session_state** (*int, None*) – The state from the output of `dumpsyst media_session`, or *None* if it was not determined
- **running_apps** (*list, None*) – A list of the running apps, or *None* if it was not determined

- **hdmi_input** (*str, None*) – The HDMI input, or *None* if it could not be determined

get_properties_dict (*get_running_apps=True, lazy=True*)

Get the properties needed for Home Assistant updates and return them as a dictionary.

Parameters

- **get_running_apps** (*bool*) – Whether or not to get the `running_apps()` property
- **lazy** (*bool*) – Whether or not to continue retrieving properties if the device is off or the screensaver is running

Returns A dictionary with keys '`screen_on`', '`awake`', '`wake_lock_size`', '`current_app`', '`media_session_state`', '`running_apps`', and '`hdmi_input`'

Return type

dict

update (*get_running_apps=True, lazy=True*)

Get the info needed for a Home Assistant update.

Parameters

- **get_running_apps** (*bool*) – Whether or not to get the `running_apps()` property
- **lazy** (*bool*) – Whether or not to continue retrieving properties if the device is off or the screensaver is running

Returns

- **state** (*str*) – The state of the device
- **current_app** (*str*) – The current running app
- **running_apps** (*list*) – A list of the running apps if `get_running_apps` is True, otherwise the list [`current_app`]
- **hdmi_input** (*str, None*) – The HDMI input, or *None* if it could not be determined

Module contents

2.1.2 Submodules

androidtv.constants module

Constants used throughout the code.

Links

- ADB key event codes
- MediaSession PlaybackState property

`androidtv.constants.CMD_AUDIO_STATE = "dumpsys audio | grep paused | grep -qv 'Buffer Queue'`
Get the audio state

`androidtv.constants.CMD_AUDIO_STATE11 = "CURRENT_AUDIO_STATE=$(dumpsys audio | sed -r -n '1q;${}`
Get the audio state for an Android 11 device

`androidtv.constants.CMD_AWAKE = 'dumpsys power | grep mWakefulness | grep -q Awake'`
Determine whether the device is awake

`androidtv.constants.CMD_CURRENT_APP = "CURRENT_APP=$(dumpsys window windows | grep -E 'mCu`
Output identifier for current/focused application

```

androidtv.constants.CMD_CURRENT_APP11 = "CURRENT_APP=$(dumpsys window windows | grep 'Window'
                                         Output identifier for current/focused application for an Android 11 device

androidtv.constants.CMD_CURRENT_APP_GOOGLE_TV = 'CURRENT_APP=$(dumpsys activity a . | grep
                                         Output identifier for current/focused application (for a Google TV device)

androidtv.constants.CMD_CURRENT_APP_MEDIA_SESSION_STATE = "CURRENT_APP=$(dumpsys window wi
                                         Determine the current app and get the state from dumpsys media_session

androidtv.constants.CMD_CURRENT_APP_MEDIA_SESSION_STATE11 = "CURRENT_APP=$(dumpsys window wi
                                         Determine the current app and get the state from dumpsys media_session for an Android 11 device

androidtv.constants.CMD_CURRENT_APP_MEDIA_SESSION_STATE_GOOGLE_TV = "CURRENT_APP=$(dumpsys ac
                                         Determine the current app and get the state from dumpsys media_session for a Google TV device

androidtv.constants.CMD_DEFINE_CURRENT_APP_VARIABLE = "CURRENT_APP=$(dumpsys window windows
                                         Assign focused application identifier to CURRENT_APP variable

androidtv.constants.CMD_DEFINE_CURRENT_APP_VARIABLE11 = "CURRENT_APP=$(dumpsys window windows
                                         Assign focused application identifier to CURRENT_APP variable for an Android 11 device

androidtv.constants.CMD_DEFINE_CURRENT_APP_VARIABLE_GOOGLE_TV = 'CURRENT_APP=$(dumpsys acti
                                         Assign focused application identifier to CURRENT_APP variable (for a Google TV device)

androidtv.constants.CMD_DEVICE_PROPERTIES = 'getprop ro.product.manufacturer && getprop ro
                                         The command used for getting the device properties

androidtv.constants.CMD_HDMI_INPUT = "dumpsys activity starter | grep -E -o '(ExternalTv|HDMI'
                                         Get the HDMI input

androidtv.constants.CMD_HDMI_INPUT11 = "(HDMI=$(dumpsys tv_input | grep 'ResourceClientPro
                                         Get the HDMI input for an Android 11 device

androidtv.constants.CMD_INSTALLED_APPS = 'pm list packages'
                                         Get installed apps

androidtv.constants.CMD_LAUNCH_APP = "CURRENT_APP=$(dumpsys window windows | grep -E 'mCur
                                         Launch an app if it is not already the current app

androidtv.constants.CMD_LAUNCH_APP11 = "CURRENT_APP=$(dumpsys window windows | grep 'Window
                                         Launch an app if it is not already the current app on an Android 11 device

androidtv.constants.CMD_LAUNCH_APP_CONDITION = "if [ $CURRENT_APP != '{0}' ]; then monkey -
                                         Launch an app if it is not already the current app (assumes the variable CURRENT_APP has already been set)

androidtv.constants.CMD_LAUNCH_APP_CONDITION_FIRETV = "if [ $CURRENT_APP != '{0}' ]; then monkey -
                                         Launch an app if it is not already the current app (assumes the variable CURRENT_APP has already been set)
                                         on a Fire TV

androidtv.constants.CMD_LAUNCH_APP_FIRETV = "CURRENT_APP=$(dumpsys window windows | grep -E 'mCur
                                         Launch an app on a Fire TV device

androidtv.constants.CMD_LAUNCH_APP_GOOGLE_TV = "CURRENT_APP=$(dumpsys activity a . | grep -E 'mCur
                                         Launch an app on a Google TV device

androidtv.constants.CMD_MEDIA_SESSION_STATE = "dumpsys media_session | grep -A 100 'Session
                                         Get the state from dumpsys media_session; this assumes that the variable CURRENT_APP has been
                                         defined

androidtv.constants.CMD_PARSE_CURRENT_APP = 'CURRENT_APP=${CURRENT_APP##*ActivityRecord{**}
                                         Parse current application identifier from dumpsys output and assign it to CURRENT_APP variable (assumes
                                         dumpsys output is momentarily set to CURRENT_APP variable)

```

```
androidtv.constants.CMD_PARSE_CURRENT_APP11 = 'CURRENT_APP=${CURRENT_APP%/*} && CURRENT_APP'
Parse current application for an Android 11 device

androidtv.constants.CMD_RUNNING_APPS_ANDROIDTV = 'ps -A | grep u0_a'
Get the running apps for an Android TV device

androidtv.constants.CMD_RUNNING_APPS_FIRETV = 'ps | grep u0_a'
Get the running apps for a Fire TV device

androidtv.constants.CMD_SCREEN_ON = "(dumpsys power | grep 'Display Power' | grep -q 'state"
Determine if the device is on

androidtv.constants.CMD_SCREEN_ON_AWAKE_WAKE_LOCK_SIZE = "(dumpsys power | grep 'Display Power' | grep -q 'state"
Determine if the device is on, the screen is on, and get the wake lock size

androidtv.constants.CMD_STREAM_MUSIC = "dumpsys audio | grep '\\\\- STREAM_MUSIC:' -A 11"
Get the "STREAM_MUSIC" block from dumpsys audio

androidtv.constants.CMD_TURN_OFF_ANDROIDTV = "(dumpsys power | grep 'Display Power' | grep -q 'KEY_POWER = 26 is defined below)"
Type Turn off an Android TV device (note

androidtv.constants.CMD_TURN_OFF_FIRETV = "(dumpsys power | grep 'Display Power' | grep -q 'KEY_SLEEP = 223 is defined below)"
Type Turn off a Fire TV device (note

androidtv.constants.CMD_TURN_ON_ANDROIDTV = "(dumpsys power | grep 'Display Power' | grep -q 'KEY_POWER = 26 is defined below)"
Type Turn on an Android TV device (note

androidtv.constants.CMD_TURN_ON_FIRETV = "(dumpsys power | grep 'Display Power' | grep -q 'KEY_POWER = 26 and KEY_HOME = 3 are defined below)"
Type Turn on a Fire TV device (note

androidtv.constants.CMD_WAKE_LOCK_SIZE = "dumpsys power | grep Locks | grep 'size='"
Get the wake lock size

androidtv.constants.DEFAULT_ADB_TIMEOUT_S = 9.0
Default timeout (in s) for adb_shell.handle.tcp_handle.TcpHandle and adb_shell.handle.
tcp_handle_async.TcpHandleAsync

androidtv.constants.DEFAULT_AUTH_TIMEOUT_S = 10.0
Default authentication timeout (in s) for adb_shell.handle.tcp_handle.TcpHandle.connect()
and adb_shell.handle.tcp_handle_async.TcpHandleAsync.connect()

androidtv.constants.DEFAULT_LOCK_TIMEOUT_S = 3.0
Default timeout for acquiring the lock that protects ADB commands

androidtv.constants.DEFAULT_TRANSPORT_TIMEOUT_S = 1.0
Default transport timeout (in s) for adb_shell.handle.tcp_handle.TcpHandle.connect() and
adb_shell.handle.tcp_handle_async.TcpHandleAsync.connect()

class androidtv.constants.DeviceEnum
Bases: enum.IntEnum

An enum for the various device types.

ANDROIDTV = 1
BASETV = 0
```

```
FIRETV = 2

androidtv.constants.HA_CUSTOMIZABLE_COMMANDS = ('audio_state', 'current_app_media_session_state')
    The subset of CUSTOMIZABLE_COMMANDS that is potentially used in the update() method

androidtv.constants.MEDIA_SESSION_STATES = {0: None, 1: 'stopped', 2: 'paused', 3: 'playing'}
    States for the media_session_state property

androidtv.constants.VALID_PROPERTIES = ('audio_state', 'media_session_state', 'wake_lock_state')
    Properties that can be checked for custom state detection (used by
    state_detection_rules_validator())

androidtv.constants.VALID_PROPERTIES_TYPES = {'audio_state': <class 'str'>, 'media_session_state': <class 'str'>}
    The required type for each entry in VALID_PROPERTIES (used by
    state_detection_rules_validator())

androidtv.constants.VALID_STATES = ('idle', 'off', 'playing', 'paused', 'standby')
    States that are valid (used by state_detection_rules_validator())

androidtv.constants.VALID_STATE_PROPERTIES = ('audio_state', 'media_session_state')
    Properties that can be used to determine the current state (used by
    state_detection_rules_validator())
```

androidtv.exceptions module

Exceptions for use throughout the code.

```
exception androidtv.exceptions.LockNotAcquiredException
    Bases: Exception
```

The ADB lock could not be acquired.

androidtv.setup_async module

Connect to a device and determine whether it's an Android TV or an Amazon Fire TV.

ADB Debugging must be enabled.

```
async androidtv.setup_async.setup(host, port=5555, adbkey='', adb_server_ip='',
                                    adb_server_port=5037, state_detection_rules=None,
                                    device_class='auto', auth_timeout_s=10.0, signer=None,
                                    transport_timeout_s=1.0)
```

Connect to a device and determine whether it's an Android TV or an Amazon Fire TV.

Parameters

- **host** (*str*) – The address of the device; may be an IP address or a host name
- **port** (*int*) – The device port to which we are connecting (default is 5555)
- **adbkey** (*str*) – The path to the adbkey file for ADB authentication
- **adb_server_ip** (*str*) – The IP address of the ADB server
- **adb_server_port** (*int*) – The port for the ADB server
- **state_detection_rules** (*dict*, *None*) – A dictionary of rules for determining the state (see *BaseTV*)
- **device_class** (*str*) – The type of device: 'auto' (detect whether it is an Android TV or Fire TV device), 'androidtv', or 'firetv'

- **auth_timeout_s** (*float*) – Authentication timeout (in seconds)
- **signer** (*PythonRSASigner, None*) – The signer for the ADB keys, as loaded by `androidtv.adb_manager.adb_manager_async.ADBPythonAsync.load_adbkey()`
- **transport_timeout_s** (*float*) – Transport timeout (in seconds)

Returns The representation of the device

Return type *AndroidTVAsync, FireTVAsync*

2.1.3 Module contents

Connect to a device and determine whether it's an Android TV or an Amazon Fire TV.

ADB Debugging must be enabled.

`androidtv.ha_state_detection_rules_validator(exc)`

Validate the rules (i.e., the `state_detection_rules` value) for a given app ID (i.e., a key in `state_detection_rules`).

See [BaseTV](#) for more info about the `state_detection_rules` parameter.

Parameters `exc` (*Exception*) – The exception that will be raised if a rule is invalid

Returns `wrapped_state_detection_rules_validator` – A function that is the same as `state_detection_rules_validator()`, but with the `exc` argument provided

Return type function

`androidtv.setup(host, port=5555, adbkey='', adb_server_ip='', adb_server_port=5037, state_detection_rules=None, device_class='auto', auth_timeout_s=10.0, signer=None, transport_timeout_s=1.0)`

Connect to a device and determine whether it's an Android TV or an Amazon Fire TV.

Parameters

- **host** (*str*) – The address of the device; may be an IP address or a host name
- **port** (*int*) – The device port to which we are connecting (default is 5555)
- **adbkey** (*str*) – The path to the adbkey file for ADB authentication
- **adb_server_ip** (*str*) – The IP address of the ADB server
- **adb_server_port** (*int*) – The port for the ADB server
- **state_detection_rules** (*dict, None*) – A dictionary of rules for determining the state (see [BaseTV](#))
- **device_class** (*str*) – The type of device: 'auto' (detect whether it is an Android TV or Fire TV device), 'androidtv', or 'firetv'
- **auth_timeout_s** (*float*) – Authentication timeout (in seconds)
- **signer** (*PythonRSASigner, None*) – The signer for the ADB keys, as loaded by `androidtv.adb_manager.adb_manager_sync.ADBPythonSync.load_adbkey()`
- **transport_timeout_s** (*float*) – Transport timeout (in seconds)

Returns The representation of the device

Return type *AndroidTVSync, FireTVSync*

CHAPTER
THREE

INSTALLATION

```
pip install androidtv
```

To utilize the async version of this code, you must install into a Python 3.7+ environment via:

```
pip install androidtv[async]
```

**CHAPTER
FOUR**

ADB INTENTS AND COMMANDS

A collection of useful intents and commands can be found [here](#) (credit: mcfrojd).

**CHAPTER
FIVE**

ACKNOWLEDGMENTS

This is based on [python-firetv](#) by [happyleaveaoc](#) and the [androidtv](#) component for Home Assistant by [alex4](#), and it depends on the Python packages [adb-shell](#) (which is based on [python-adb](#)) and [pure-python-adb](#).

**CHAPTER
SIX**

INDICES AND TABLES

- genindex
- modindex
- search

PYTHON MODULE INDEX

a

androidtv, 48
androidtv.adb_manager, 11
androidtv.adb_manager.adb_manager_async,
 5
androidtv.adb_manager.adb_manager_sync,
 9
androidtv.androidtv, 16
androidtv.androidtv.androidtv_async, 11
androidtv.androidtv.androidtv_sync, 13
androidtv.androidtv.base_androidtv, 15
androidtv.basetv, 40
androidtv.basetv.basetv, 17
androidtv.basetv.basetv_async, 23
androidtv.basetv.basetv_sync, 31
androidtv.constants, 44
androidtv.exceptions, 47
androidtv.firetv, 44
androidtv.firetv.base_firetv, 40
androidtv.firetv.firetv_async, 41
androidtv.firetv.firetv_sync, 42
androidtv.setup_async, 47

INDEX

Symbols

_acquire()	(in module <i>an-</i>	<i>droidtv.adb_manager.adb_manager_async</i>),	20	
	8			
_acquire()	(in module <i>an-</i>	<i>droidtv.adb_manager.adb_manager_sync</i>),	20	
	11			
_audio_output_device()	(an-	<i>droidtv.basetv.basetv.BaseTV static method</i>),	20	
	18			
_audio_state()	(<i>androidtv.basetv.basetv.BaseTV static method</i>),	20		18
_cmd_audio_state()	(<i>an-</i>	<i>droidtv.basetv.basetv.BaseTV method</i>),	20	18
_cmd_current_app()	(an-	<i>droidtv.basetv.basetv.BaseTV method</i>),	20	18
_cmd_current_app_media_session_state()	(<i>an-</i>	<i>droidtv.basetv.basetv.BaseTV method</i>),	20	18
_cmd_hdmi_input()	(an-	<i>droidtv.basetv.basetv.BaseTV method</i>),	20	18
_cmd_launch_app()	(an-	<i>droidtv.basetv.basetv.BaseTV method</i>),	20	18
_cmd_running_apps()	(an-	<i>droidtv.basetv.basetv.BaseTV method</i>),	20	18
_cmd_turn_off()	(<i>an-</i>	<i>droidtv.basetv.basetv.BaseTV static method</i>),	21	19
_cmd_turn_on()	(<i>an-</i>	<i>droidtv.basetv.basetv.BaseTV static method</i>),	21	19
_conditions_are_true()	(<i>an-</i>	<i>droidtv.basetv.basetv.BaseTV static method</i>),	21	19
_current_app()	(<i>androidtv.basetv.basetv.BaseTV static method</i>),	21		19
_current_app_media_session_state()	(<i>an-</i>	<i>androidtv.basetv.basetv.BaseTV method</i>),	21	
_custom_state_detection()	(an-	<i>droidtv.basetv.basetv.BaseTV method</i>),	21	
_get_hdmi_input()	(an-	<i>droidtv.basetv.basetv.BaseTV static method</i>),	21	
_get_installed_apps()	(an-	<i>droidtv.basetv.basetv.BaseTV static method</i>),	21	
		<i>droidtv.basetv.basetv_async.BaseTVAsync method</i>),	24	
		<i>droidtv.basetv.basetv_sync.BaseTVSync method</i>),	32	
		<i>droidtv.basetv.basetv.BaseTV static method</i>),	32	
		<i>droidtv.basetv.basetv.AsyncBaseTVAsync method</i>),	24	
		<i>droidtv.basetv.basetv.SyncBaseTVSync method</i>),	32	
		<i>droidtv.basetv.basetv.BaseTV static method</i>),	20	
		<i>droidtv.basetv.basetv.BaseTV method</i>),	20	
		<i>droidtv.basetv.basetv.BaseTV static method</i>),	20	
		<i>droidtv.basetv.basetv.BaseTV static method</i>),	20	
		<i>droidtv.basetv.basetv.BaseTV static method</i>),	21	
		<i>droidtv.basetv.basetv.BaseTV static method</i>),	21	
		<i>droidtv.basetv.basetv.BaseTV static method</i>),	21	
		<i>droidtv.basetv.basetv.BaseTV static method</i>),	21	
		<i>droidtv.basetv.basetv.AsyncBaseTVAsync method</i>),	24	
		<i>droidtv.basetv.basetv.SyncBaseTVSync method</i>),	32	
		<i>droidtv.basetv.basetv.BaseTV static method</i>),	16	
		<i>droidtv.firetv.base_firetv.BaseFireTV</i> (an-	16	

method), 40
_volume() (androidtv.basetv.basetv.BaseTV method), 21
_volume_level() (androidtv.basetv.basetv.BaseTV method), 22
_wake_lock_size() (androidtv.basetv.basetv.BaseTV static method), 22

A

adb_close() (androidtv.basetv.basetv_async.BaseTVAsync method), 24
adb_close() (androidtv.basetv.basetv_sync.BaseTVSync method), 33
adb_connect() (androidtv.basetv.basetv_async.BaseTVAsync method), 24
adb_connect() (androidtv.basetv.basetv_sync.BaseTVSync method), 33
adb_pull() (androidtv.basetv.basetv_async.BaseTVAsync method), 25
adb_pull() (androidtv.basetv.basetv_sync.BaseTVSync method), 33
adb_push() (androidtv.basetv.basetv_async.BaseTVAsync method), 25
adb_push() (androidtv.basetv.basetv_sync.BaseTVSync method), 33
adb_screencap() (androidtv.basetv.basetv_async.BaseTVAsync method), 25
adb_screencap() (androidtv.basetv.basetv_sync.BaseTVSync method), 33
adb_shell() (androidtv.basetv.basetv_async.BaseTVAsync method), 25
adb_shell() (androidtv.basetv.basetv_sync.BaseTVSync method), 34
AdbDeviceUsbAsync (class in androidtv.adb_manager.adb_manager_async), 7
ADBPythonAsync (class in androidtv.adb_manager.adb_manager_async), 5
ADBPythonSync (class in androidtv.adb_manager.adb_manager_sync), 9
ADBServerAsync (class in androidtv.adb_manager.adb_manager_async), 6
ADBServerSync (class in androidtv.adb_manager.adb_manager_sync), 10

ANDROIDTV (androidtv.constants.DeviceEnum attribute), 46
androidtv (module), 48
androidtv.adb_manager (module), 11
androidtv.adb_manager.adb_manager_async (module), 5
androidtv.adb_manager.adb_manager_sync (module), 9
androidtv.androidtv (module), 16
androidtv.androidtv.androidtv_async (module), 11
androidtv.androidtv.androidtv_sync (module), 13
androidtv.androidtv.base_androidtv (module), 15
androidtv.basetv (module), 40
androidtv.basetv.basetv (module), 17
androidtv.basetv.basetv_async (module), 23
androidtv.basetv.basetv_sync (module), 31
androidtv.constants (module), 44
androidtv.exceptions (module), 47
androidtv.firetv (module), 44
androidtv.firetv.base_firetv (module), 40
androidtv.firetv.firetv_async (module), 41
androidtv.firetv.firetv_sync (module), 42
androidtv.setup_async (module), 47
AndroidTVAsync (class in androidtv.androidtv.async), 11
AndroidTVSync (class in androidtv.androidtv.sync), 13
audio_output_device() (androidtv.basetv.basetv_async.BaseTVAsync method), 25
audio_output_device() (androidtv.basetv.basetv_sync.BaseTVSync method), 34
audio_state() (androidtv.basetv.basetv_async.BaseTVAsync method), 25
audio_state() (androidtv.basetv.basetv_sync.BaseTVSync method), 34
available() (androidtv.adb_manager.adb_manager_async.AdbDeviceUsb property), 8
available() (androidtv.adb_manager.adb_manager_async.ADBPython property), 5
available() (androidtv.adb_manager.adb_manager_async.ADBServer property), 7
available() (androidtv.adb_manager.adb_manager_sync.ADBPythonSync property), 9
available() (androidtv.adb_manager.adb_manager_sync.ADBServerSync property), 10
available() (androidtv.basetv.basetv.BaseTV property), 22

awake() (*androidtv.basetv.basetv_async.BaseTVAsync method*), 26
 awake() (*androidtv.basetv.basetv_sync.BaseTVSync method*), 34

B

back() (*androidtv.basetv.basetv_async.BaseTVAsync method*), 26
 back() (*androidtv.basetv.basetv_sync.BaseTVSync method*), 34
 BaseAndroidTV (class in *androidtv.androidtv.base_androidtv*), 15
 BaseFireTV (class in *androidtv.firetv.base_firetv*), 40
 BASETV (*androidtv.constants.DeviceEnum attribute*), 46
 BaseTV (class in *androidtv.basetv.basetv*), 17
 BaseTVAsync (class in *androidtv.basetv.basetv_async*), 23
 BaseTVSync (class in *androidtv.basetv.basetv_sync*), 31

C

ClientAsync (class in *androidtv.adb_manager.adb_manager_async*), 8
 close() (*androidtv.adb_manager.adb_manager_async.AdbDeviceUsbAsync method*), 8
 close() (*androidtv.adb_manager.adb_manager_async.ADBPythonAsync method*), 5
 close() (*androidtv.adb_manager.adb_manager_async.ADBServerAsync method*), 7
 close() (*androidtv.adb_manager.adb_manager_sync.ADBPythonSync method*), 9
 close() (*androidtv.adb_manager.adb_manager_sync.ADBServerSync method*), 10
 CMD_AUDIO_STATE (in module *androidtv.constants*), 44
 CMD_AUDIO_STATE11 (in module *androidtv.constants*), 44
 CMD_AWAKE (in module *androidtv.constants*), 44
 CMD_CURRENT_APP (in module *androidtv.constants*), 44
 CMD_CURRENT_APP11 (in module *androidtv.constants*), 45
 CMD_CURRENT_APP_GOOGLE_TV (in module *androidtv.constants*), 45
 CMD_CURRENT_APP_MEDIA_SESSION_STATE (in module *androidtv.constants*), 45
 CMD_CURRENT_APP_MEDIA_SESSION_STATE11 (in module *androidtv.constants*), 45
 CMD_CURRENT_APP_MEDIA_SESSION_STATE_GOOGLE (in module *androidtv.constants*), 45
 CMD_DEFINE_CURRENT_APP_VARIABLE (in module *androidtv.constants*), 45
 CMD_DEFINE_CURRENT_APP_VARIABLE11 (in module *androidtv.constants*), 45
 CMD_DEFINE_CURRENT_APP_VARIABLE_GOOGLE_TV (in module *androidtv.constants*), 45
 CMD_DEVICE_PROPERTIES (in module *androidtv.constants*), 45
 CMD_HDMI_INPUT (in module *androidtv.constants*), 45
 CMD_HDMI_INPUT11 (in module *androidtv.constants*), 45
 CMD_INSTALLED_APPS (in module *androidtv.constants*), 45
 CMD_LAUNCH_APP (in module *androidtv.constants*), 45
 CMD_LAUNCH_APP11 (in module *androidtv.constants*), 45
 CMD_LAUNCH_APP_CONDITION (in module *androidtv.constants*), 45
 CMD_LAUNCH_APP_CONDITION_FIRETV (in module *androidtv.constants*), 45
 CMD_LAUNCH_APP_FIRETV (in module *androidtv.constants*), 45
 CMD_LAUNCH_APP_GOOGLE_TV (in module *androidtv.constants*), 45
 CMD_MEDIA_SESSION_STATE (in module *androidtv.constants*), 45
 CMD_PARSE_CURRENT_APP (in module *androidtv.constants*), 45
 CMD_PARSE_CURRENT_APP11 (in module *androidtv.constants*), 45
 CMD_RUNNING_APPS_ANDROIDTV (in module *androidtv.constants*), 46
 CMD_RUNNING_APPS_FIRETV (in module *androidtv.constants*), 46
 CMD_SCREEN_ON (in module *androidtv.constants*), 46
 CMD_SCREEN_ON_WAKE_LOCK_SIZE (in module *androidtv.constants*), 46
 CMD_STREAM_MUSIC (in module *androidtv.constants*), 46
 CMD_TURN_OFF_ANDROIDTV (in module *androidtv.constants*), 46
 CMD_TURN_OFF_FIRETV (in module *androidtv.constants*), 46
 CMD_TURN_ON_ANDROIDTV (in module *androidtv.constants*), 46
 CMD_TURN_ON_FIRETV (in module *androidtv.constants*), 46
 CMD_WAKE_LOCK_SIZE (in module *androidtv.constants*), 46
 connect() (*androidtv.adb_manager.adb_manager_async.AdbDeviceUsbAsync method*), 8
 connect() (*androidtv.adb_manager.adb_manager_async.ADBPythonAsync method*), 5
 connect() (*androidtv.adb_manager.adb_manager_async.ADBServerAsync method*), 7
 connect() (*androidtv.adb_manager.adb_manager_sync.ADBPythonSync method*)

method), 9

connect () (androidtv.adb_manager.adb_manager_sync.ADBServerSync
method), 10

current_app () (an-
droidtv.basetv.basetv_async.BaseTVAsync
method), 26

current_app () (an-
droidtv.basetv.basetv_sync.BaseTVSync
method), 34

current_app_media_session_state () (an-
droidtv.basetv.basetv_async.BaseTVAsync
method), 26

current_app_media_session_state () (an-
(androidtv.basetv.basetv_sync.BaseTVSync
method), 34

customize_command () (an-
droidtv.basetv.basetv.BaseTV method), 22

D

DEFAULT_ADB_TIMEOUT_S (in module an-
droidtv.constants), 46

DEFAULT_AUTH_TIMEOUT_S (in module an-
droidtv.constants), 46

DEFAULT_LOCK_TIMEOUT_S (in module an-
droidtv.constants), 46

DEFAULT_TRANSPORT_TIMEOUT_S (in module an-
droidtv.constants), 46

device () (androidtv.adb_manager.adb_manager_async.ClientAsync
method), 8

DEVICE_CLASS (androidtv.androidtv.base_androidtv.BaseAndroidTV
attribute), 16

DEVICE_CLASS (androidtv.firetv.base_firetv.BaseFireTV
attribute), 40

DEVICE_ENUM (androidtv.androidtv.base_androidtv.BaseAndroidTV
attribute), 16

DEVICE_ENUM (androidtv.basetv.basetv.BaseTV at-
tribute), 18

DEVICE_ENUM (androidtv.firetv.base_firetv.BaseFireTV
attribute), 40

DeviceAsync (class in an-
droidtv.adb_manager.adb_manager_async), 8

DeviceEnum (class in androidtv.constants), 46

down () (androidtv.basetv.basetv_async.BaseTVAsync
method), 26

down () (androidtv.basetv.basetv_sync.BaseTVSync
method), 34

E

enter () (androidtv.basetv.basetv_async.BaseTVAsync
method), 26

enter () (androidtv.basetv.basetv_sync.BaseTVSync
method), 34

F

FireTVSync (class in androidtv.firetv.firetv_async), 41

FireTVSync (class in androidtv.firetv.firetv_sync), 43

from_base () (androidtv.androidtv.androidtv_async.AndroidTVAsync
class method), 12

from_base () (androidtv.androidtv.androidtv_sync.AndroidTVSync
class method), 14

from_base () (androidtv.firetv.firetv_async.FireTVAsync
class method), 41

from_base () (androidtv.firetv.firetv_sync.FireTVSync
class method), 43

G

get_device_properties () (an-
droidtv.basetv.basetv_async.BaseTVAsync
method), 26

get_device_properties () (an-
droidtv.basetv.basetv_sync.BaseTVSync
method), 35

get_hdmi_input () (an-
droidtv.basetv.basetv_async.BaseTVAsync
method), 26

get_hdmi_input () (an-
droidtv.basetv.basetv_sync.BaseTVSync
method), 35

get_installed_apps () (an-
droidtv.basetv.basetv_async.BaseTVAsync
method), 26

get_installed_apps () (an-
droidtv.basetv.basetv_sync.BaseTVSync
method), 35

get_properties () (an-
droidtv.androidtv.androidtv_async.AndroidTVAsync
method), 12

get_properties () (an-
droidtv.androidtv.androidtv_sync.AndroidTVSync
method), 14

get_properties () (an-
droidtv.firetv.firetv_async.FireTVAsync
method), 41

get_properties () (an-
droidtv.firetv.firetv_sync.FireTVSync method), 43

get_properties_dict () (an-
droidtv.androidtv.androidtv_async.AndroidTVAsync
method), 13

get_properties_dict () (an-
droidtv.androidtv.androidtv_sync.AndroidTVSync
method), 14

get_properties_dict () (an-
droidtv.firetv.firetv_async.FireTVAsync
method), 42

get_properties_dict() (androidtv.firetv.firetv_sync.FireTVSync method), 44

H

HA_CUSTOMIZABLE_COMMANDS (in module androidtv.constants), 47

ha_state_detection_rules_validator() (in module androidtv), 48

home() (androidtv.basetv.basetv_async.BaseTVAync method), 26

home() (androidtv.basetv.basetv_sync.BaseTVSync method), 35

I

is_volume_muted() (androidtv.basetv.basetv_async.BaseTVAync method), 26

is_volume_muted() (androidtv.basetv.basetv_sync.BaseTVSync method), 35

K

key_0() (androidtv.basetv.basetv_async.BaseTVAync method), 27

key_0() (androidtv.basetv.basetv_sync.BaseTVSync method), 35

key_1() (androidtv.basetv.basetv_async.BaseTVAync method), 27

key_1() (androidtv.basetv.basetv_sync.BaseTVSync method), 35

key_2() (androidtv.basetv.basetv_async.BaseTVAync method), 27

key_2() (androidtv.basetv.basetv_sync.BaseTVSync method), 35

key_3() (androidtv.basetv.basetv_async.BaseTVAync method), 27

key_3() (androidtv.basetv.basetv_sync.BaseTVSync method), 35

key_4() (androidtv.basetv.basetv_async.BaseTVAync method), 27

key_4() (androidtv.basetv.basetv_sync.BaseTVSync method), 35

key_5() (androidtv.basetv.basetv_async.BaseTVAync method), 27

key_5() (androidtv.basetv.basetv_sync.BaseTVSync method), 35

key_6() (androidtv.basetv.basetv_async.BaseTVAync method), 27

key_6() (androidtv.basetv.basetv_sync.BaseTVSync method), 35

key_7() (androidtv.basetv.basetv_async.BaseTVAync method), 27

key_7() (androidtv.basetv.basetv_sync.BaseTVSync method), 35

key_8() (androidtv.basetv.basetv_async.BaseTVAync method), 27

key_8() (androidtv.basetv.basetv_sync.BaseTVSync method), 35

key_9() (androidtv.basetv.basetv_async.BaseTVAync method), 27

key_9() (androidtv.basetv.basetv_sync.BaseTVSync method), 35

key_a() (androidtv.basetv.basetv_async.BaseTVAync method), 27

key_a() (androidtv.basetv.basetv_sync.BaseTVSync method), 35

key_b() (androidtv.basetv.basetv_async.BaseTVAync method), 27

key_b() (androidtv.basetv.basetv_sync.BaseTVSync method), 36

key_c() (androidtv.basetv.basetv_async.BaseTVAync method), 27

key_c() (androidtv.basetv.basetv_sync.BaseTVSync method), 36

key_d() (androidtv.basetv.basetv_async.BaseTVAync method), 27

key_d() (androidtv.basetv.basetv_sync.BaseTVSync method), 36

key_e() (androidtv.basetv.basetv_async.BaseTVAync method), 27

key_e() (androidtv.basetv.basetv_sync.BaseTVSync method), 36

key_f() (androidtv.basetv.basetv_async.BaseTVAync method), 27

key_f() (androidtv.basetv.basetv_sync.BaseTVSync method), 36

key_g() (androidtv.basetv.basetv_async.BaseTVAync method), 27

key_g() (androidtv.basetv.basetv_sync.BaseTVSync method), 36

key_h() (androidtv.basetv.basetv_async.BaseTVAync method), 27

key_h() (androidtv.basetv.basetv_sync.BaseTVSync method), 36

key_i() (androidtv.basetv.basetv_async.BaseTVAync method), 27

key_i() (androidtv.basetv.basetv_sync.BaseTVSync method), 36

key_j() (androidtv.basetv.basetv_async.BaseTVAync method), 27

key_j() (androidtv.basetv.basetv_sync.BaseTVSync method), 36

key_k() (androidtv.basetv.basetv_async.BaseTVAync method), 27

key_k() (androidtv.basetv.basetv_sync.BaseTVSync method), 36

key_l () (*androidtv.basetv.basetv_async.BaseTVAsync method*), 27
key_l () (*androidtv.basetv.basetv_sync.BaseTVSync method*), 36
key_m () (*androidtv.basetv.basetv_async.BaseTVAsync method*), 28
key_m () (*androidtv.basetv.basetv_sync.BaseTVSync method*), 36
key_n () (*androidtv.basetv.basetv_async.BaseTVAsync method*), 28
key_n () (*androidtv.basetv.basetv_sync.BaseTVSync method*), 36
key_o () (*androidtv.basetv.basetv_async.BaseTVAsync method*), 28
key_o () (*androidtv.basetv.basetv_sync.BaseTVSync method*), 36
key_p () (*androidtv.basetv.basetv_async.BaseTVAsync method*), 28
key_p () (*androidtv.basetv.basetv_sync.BaseTVSync method*), 36
key_q () (*androidtv.basetv.basetv_async.BaseTVAsync method*), 28
key_q () (*androidtv.basetv.basetv_sync.BaseTVSync method*), 36
key_r () (*androidtv.basetv.basetv_async.BaseTVAsync method*), 28
key_r () (*androidtv.basetv.basetv_sync.BaseTVSync method*), 36
key_s () (*androidtv.basetv.basetv_async.BaseTVAsync method*), 28
key_s () (*androidtv.basetv.basetv_sync.BaseTVSync method*), 36
key_t () (*androidtv.basetv.basetv_async.BaseTVAsync method*), 28
key_t () (*androidtv.basetv.basetv_sync.BaseTVSync method*), 36
key_u () (*androidtv.basetv.basetv_async.BaseTVAsync method*), 28
key_u () (*androidtv.basetv.basetv_sync.BaseTVSync method*), 36
key_v () (*androidtv.basetv.basetv_async.BaseTVAsync method*), 28
key_v () (*androidtv.basetv.basetv_sync.BaseTVSync method*), 36
key_w () (*androidtv.basetv.basetv_async.BaseTVAsync method*), 28
key_w () (*androidtv.basetv.basetv_sync.BaseTVSync method*), 37
key_x () (*androidtv.basetv.basetv_async.BaseTVAsync method*), 28
key_x () (*androidtv.basetv.basetv_sync.BaseTVSync method*), 37
key_y () (*androidtv.basetv.basetv_async.BaseTVAsync method*), 28
key_y () (*androidtv.basetv.basetv_sync.BaseTVSync method*), 37
key_z () (*androidtv.basetv.basetv_async.BaseTVAsync method*), 28
key_z () (*androidtv.basetv.basetv_sync.BaseTVSync method*), 37

L

launch_app () (*androidtv.basetv.basetv_async.BaseTVAsync method*), 28
launch_app () (*androidtv.basetv.basetv_sync.BaseTVSync method*), 37
learn_sendevent () (*androidtv.basetv.basetv_async.BaseTVAsync method*), 28
learn_sendevent () (*androidtv.basetv.basetv_sync.BaseTVSync method*), 37
left () (*androidtv.basetv.basetv_async.BaseTVAsync method*), 28
left () (*androidtv.basetv.basetv_sync.BaseTVSync method*), 37
load_adbkey () (*androidtv.adb_manager.adb_manager_async.ADBPythonAsync static method*), 6
load_adbkey () (*androidtv.adb_manager.adb_manager_sync.ADBPythonSync static method*), 9
LOCK_KWARGS (*in module androidtv.adb_manager.adb_manager_sync*), 11
LockNotAcquiredException, 47

M

media_next_track () (*androidtv.basetv.basetv_async.BaseTVAsync method*), 29
media_next_track () (*androidtv.basetv.basetv_sync.BaseTVSync method*), 37
media_pause () (*androidtv.basetv.basetv_async.BaseTVAsync method*), 29
media_pause () (*androidtv.basetv.basetv_sync.BaseTVSync method*), 37
media_play () (*androidtv.basetv.basetv_async.BaseTVAsync method*), 29
media_play () (*androidtv.basetv.basetv_sync.BaseTVSync method*), 37
media_play_pause () (*androidtv.basetv.basetv_async.BaseTVAsync method*), 29

```
media_play_pause()
    droidtv.basetv.basetv_sync.BaseTWSync
        method), 37
media_previous_track()
    droidtv.basetv.basetv_async.BaseTVAsync
        method), 29
media_previous_track()
    droidtv.basetv.basetv_sync.BaseTWSync
        method), 37
media_session_state()
    droidtv.basetv.basetv_async.BaseTVAsync
        method), 29
media_session_state()
    droidtv.basetv.basetv_sync.BaseTWSync
        method), 37
MEDIA_SESSION_STATES      (in      module
    droidtv.constants), 47
media_stop() (androidtv.basetv.basetv_async.Ba
        method), 29
media_stop() (androidtv.basetv.basetv_sync.Base
        method), 37
menu()   (androidtv.basetv.basetv_async.BaseTVA
        method), 29
menu()   (androidtv.basetv.basetv_sync.BaseTV
        method), 37
mute_volume()
    droidtv.basetv.basetv_async.BaseTVAsync
        method), 29
mute_volume()
    droidtv.basetv.basetv_sync.BaseTWSync
        method), 38
```

(an- push () (*androidtv.adb_manager.adb_manager_async.ADBServerAsync method*), 7
(an- push () (*androidtv.adb_manager.adb_manager_async.DeviceAsync method*), 8
push () (*androidtv.adb_manager.adb_manager_sync.ADBPythonSync method*), 9
(an- push () (*androidtv.adb_manager.adb_manager_sync.ADBServerSync method*), 11

R

right () (*androidtv.basetv.basetv_async.BaseTVAsync method*), 29
(an- right () (*androidtv.basetv.basetv_sync.BaseTVSync method*), 38
running_apps () (an-
an- *droidtv.basetv.basetv_async.BaseTVAsync method*), 29
~~aseTVAsync~~ running_apps () (an-
~~seTVSync~~ *droidtv.basetv.basetv_sync.BaseTVSync method*), 38

S

screen_on () (*androidtv.basetv.basetv_async.BaseTVAsync method*), 29
(an- screen_on () (*androidtv.basetv.basetv_sync.BaseTVSync method*), 38
screen_on_awake_wake_lock_size () (an-
an- *droidtv.basetv.basetv_async.BaseTVAsync method*), 29
screen_on_awake_wake_lock_size () (an-
an- *droidtv.basetv.basetv_sync.BaseTVSync method*), 38
screencap () (*androidtv.adb_manager.adb_manager_async.ADBPython method*), 6
screencap () (*androidtv.adb_manager.adb_manager_async.ADBServerSync.AdbDeviceUsbAyncMethod*), 8
screencap () (*androidtv.adb_manager.adb_manager_async.DeviceAsync Aync.AdbDeviceUsbAyncMethod*), 8
screencap () (*androidtv.adb_manager.adb_manager_sync.ADBPythonAsynnc.ADBPythonAsynmethod*), 10
screencap () (*androidtv.adb_manager.adb_manager_sync.ADBServerSync.ADBServerAsynmethod*), 11
set_volume_level () (an-
ync.DeviceAsync *droidtv.basetv.basetv_async.BaseTVAsync method*), 29
nc.ADBPythonSync set_volume_level () (an-
nc.ADBServerSync *droidtv.basetv.basetv_sync.BaseTVSync method*), 38
setup () (*in module androidtv*), 48
ync.AdbDeviceUsbAync setup () (*in module androidtv.setup_async*), 47
shell () (*androidtv.adb_manager.adb_manager_async.AdbDeviceUsbAync.ADBPythonAsynmethod*), 8
shell () (*androidtv.adb_manager.adb_manager_async.ADBPythonAsyn method*), 6

```

shell() (androidtv.adb_manager.adb_manager_async.ADBServerSync (androidtv.firetv.firetv_async.FireTVAsync
    method), 7
shell() (androidtv.adb_manager.adb_manager_async.DeviceAsync) (androidtv.firetv.firetv_sync.FireTVSync
    method), 8
shell() (androidtv.adb_manager.adb_manager_sync.ADBPythonSync
    method), 10
shell() (androidtv.adb_manager.adb_manager_sync.ADBServerSync VALID_PROPERTIES (in module androidtv.constants),
    method), 11
sleep() (androidtv.basetv.basetv_async.BaseTVAsync VALID_PROPERTIES_TYPES (in module androidtv.constants),
    method), 30
sleep() (androidtv.basetv.basetv_sync.BaseTVSync VALID_STATE_PROPERTIES (in module androidtv.constants),
    method), 38
space() (androidtv.basetv.basetv_async.BaseTVAsync VALID_STATES (in module androidtv.constants),
    method), 30
space() (androidtv.basetv.basetv_sync.BaseTVSync volume() (androidtv.basetv.basetv_async.BaseTVAsync
    method), 38
    method), 38
start_intent() (an- volume() (androidtv.basetv.basetv_sync.BaseTVSync
    droidtv.basetv.basetv_async.BaseTVAsync method), 30
    method), 39
start_intent() (an- volume() (androidtv.basetv.basetv_async.BaseTVAsync
    droidtv.basetv.basetv_sync.BaseTVSync method), 38
    method), 39
state_detection_rules_validator() (in volume() (androidtv.basetv.basetv_async.BaseTVAsync
    module androidtv.basetv.basetv), 22
    method), 31
stop_app() (androidtv.basetv.basetv_async.BaseTVAsync volume_level() (an-
    method), 30
    droidtv.basetv.basetv_sync.BaseTVSync droidtv.basetv.basetv_async.BaseTVAsync
    method), 38
    method), 31
stop_app() (androidtv.basetv.basetv_sync.BaseTVSync volume_level() (an-
    method), 38
    droidtv.basetv.basetv_sync.BaseTVSync droidtv.basetv.basetv_sync.BaseTVSync
    method), 39
    method), 39
stream_music_properties() (an- volume_up() (androidtv.basetv.basetv_async.BaseTVAsync
    droidtv.basetv.basetv_async.BaseTVAsync method), 30
    method), 31
stream_music_properties() (an- volume_up() (androidtv.basetv.basetv_sync.BaseTVSync
    droidtv.basetv.basetv_sync.BaseTVSync method), 39
    method), 39

```

T

```

turn_off() (androidtv.basetv.basetv_async.BaseTVAsync
    method), 30
turn_off() (androidtv.basetv.basetv_sync.BaseTVSync
    method), 39
turn_on() (androidtv.basetv.basetv_async.BaseTVAsync
    method), 30
turn_on() (androidtv.basetv.basetv_sync.BaseTVSync
    method), 39

```

U

```

up() (androidtv.basetv.basetv_async.BaseTVAsync
    method), 30
up() (androidtv.basetv.basetv_sync.BaseTVSync
    method), 39
update() (androidtv.androidtv.androidtv_async.AndroidTVAsync
    method), 13
update() (androidtv.androidtv.androidtv_sync.AndroidTVSync
    method), 15

```

W

```

wake_lock_size() (an- wake_lock_size() (an-
    droidtv.basetv.basetv_async.BaseTVAsync
    method), 31
    droidtv.basetv.basetv_sync.BaseTVSync
    method), 31

```